

# Configuring Java heap space for Cassandra and TWCloud

This page provides instructions for changing the Java heap space (Xmx) for both Cassandra and TWCloud on Linux and Windows, respectively.

- [Configuring Java heap space for Cassandra](#)
  - [On Linux](#)
  - [On Windows](#)
- [Configuring Java heap space for TWCloud](#)
  - [On Linux](#)
  - [On Windows](#)

## Configuring Java heap space for Cassandra

### On Linux

To configure Java heap space for Cassandra on Linux, you must set it from the variables, `MAX_HEAP_SIZE` and `HEAP_NEWSIZE` which are commented by default in the file `cassandra-env.sh`. The location of the file `cassandra-env.sh` depends on the type of Cassandra installation.

- Package installation: `/etc/cassandra/cassandra-env.sh`
- Tarball installation: `<Cassandra install folder>/conf/cassandra-env.sh`

Uncomment `MAX_HEAP_SIZE`, `HEAP_NEWSIZE` variables and adjust `MAX_HEAP_SIZE` manually. Otherwise, Cassandra will calculate the heap size based on the system's memory using the following formula:

#### Calculating Java heap size

```
max(min (1/2 ram), 1024MB), min(1/4 ram, 8GB))
```

The formula details are outlined below:

- For the system memory 0-2 GB: use half of it.
- For the system memory 2-4 GB: use 1 GB.
- For the system memory 4-32 GB: use a quarter of it.
- For the system memory more than 32 GB: use 8 GB.

### On Windows

We recommend setting the **min (-Xms)** and **max (-Xmx)** heap to the same value in the Cassandra document to avoid pausing the GC during resizing.

To change the value using the Registry Editor

1. Run `regedit` from the command line
2. Browse for the key `HKEY_LOCAL_MACHINE\SOFTWARE\WOW6432Node\Apache Software Foundation\Procrun 2.0\cassandra\Parameters\Java`.
3. Right-click **Options** and select **Modify....** You can then change the min and max heap size from **-Xms** and **-Xmx**.

## Configuring Java heap space for TWCloud

### On Linux

- Max heap space for the twcloud service is configured by editing the **-Xmx** in `twcloud.ini` (located in the installation folder).

### On Windows

- If you start TWCloud from the executable file `twcloud.exe`, you can configure the **-Xmx** parameter from the file `twcloud.ini` (located in the same folder).
- If you start TWCloud from a Windows service, you must use the Registry Editor to update the value.

To change the value using the Registry Editor

1. Run regedit from the command line.
2. Browse for the key *HKEY\_LOCAL\_MACHINE\SOFTWARE\WOW6432Node\Apache Software Foundation\Procrun 2.0\Teamwork Cloud\Parameters\Java*.
3. Right-click **JvmMx** and select **Modify...**
4. Select **Base to Decimal** and change the value. The value is in megabytes (mb).