

SAML parameters

To integrate the Authentication Server with any SAML Identity Provider, you need to add the Authentication Server configuration into the SAML Identity Provider (it should be registered as SAML V2 remote service provider). Next, you need to configure the following additional parameters in the **authserver.properties** file.

| Parameter | Description | Default value |
|---------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------------------------------------------------|
| authentication.saml.enabled | Sets the value to true . | false |
| authentication.saml.entity.id | Sets an authentication server as a service provider ID if it is different than the default server. | com.nomagic.authentication.server |
| authentication.saml.name.id.format | Specifies the format of a username identifier. | urn:oasis:names:tc:SAML:1.1:nameid-format:X509SubjectName |
| authentication.saml.idp.metadata.url | Specifies an Identity Provider metadata URL address if SAML Identity Provider supports metadata retrieval from the URL (e.g., ForgeRock OpenAM). | - |
| authentication.saml.idp.metadata.file | Specifies the name of a metadata file, which should be added into the same config directory where the authserver.properties file exists. This metadata file is required by some Identity Providers instead of metadata URL (e.g., WSO2 Identity Service). | - |
| authentication.saml.link | The title of the button for SAML user login displayed on the login page. | SAML User |

Related pages

- [SAML integration](#)