

Java Annotation Member

A Java annotation member is mapped directly to the UML Operation owned by the interface stereotyped as «JavaAnnotation». This operation, by itself, can have the stereotype «JavaAnnotationMember». However, it is optional, unless specify a default value for it.

A Java annotation member type is mapped to a UML Type property of a UML Parameter with the "Return" direction kind.

Annotation member mapping table:

Java Element	UML element
Annotation member declaration	UML Operation with the stereotype «JavaAnnotationMember» (Optional), owned by a UML Interface with the stereotype «JavaAnnotation».
Annotation member name	UML Operation Name
Annotation member documentation	UML Operation Documentation
Annotation member type	Mapped to the UML Parameter type with the "return" direction kind (resides in UML Operation parameters list)
Annotation member type modifier	Mapped to the MagicDraw specified property "Type Modifier"
Default value	{JavaAnnotationMemberDefaultValue} tagged value of a «JavaAnnotationMember» stereotype. The stereotype is set on UML Operation

 **Example**
Java source code

```
Re /**
 * Comment of annotation
 */
public @interface Annotation
{
    int id();
    String name() default "[unassigned]";
}
```

- UML model
- [Java Annotation Member](#)
 - [Java Annotations Usage](#)
 - [Java Type Variables](#)
 - [Java Parameterized Type](#)
 - [Java Imports](#)