# **Recording Verification status of runtime values**

### On this page

#### • Remember Failure Status option


Cameo Simulation Toolkit supports recording verification status of runtime values. You can verify and record the status of constraints during runtime. If constraints are not met during the simulation, cells in the Requirement/Instance table will be highlighted in red on the **Variables** pane. You can do the normal recording verification status of runtime values by using the resultLocation tag in SimulationConfig. The instances with recorded values in slots are created at the end of simulation.

The Requirement(s) table shows that the constraint in the requirement is not met, thus the requirement is colored in red as follows

٠	) i Be	Add New 🔛 Add Nested 🋄 Add	Existing 🍵 Delete 🖷 Remove From Table 🧯 🎓 🐗 Unnest 📲 Nest 🦂 Sho	v Columns	🤅 🛅 Export 🕴 💋 🔍 🔍 🔍	100% 🗸 🗄 🕼 🕴 🗘 🗸	Report V	
#	Id	Name	Text		Satisfied By	Design Value	<ul> <li>Verification Sta</li> </ul>	
1	1	R Weight	The gross weight of the car <u>shall be no more than</u> 1700 kg		[ veight : kg = 1800.0 [Car]	20. 1800.0 [Car::weight]		
Variables								
₿ Variables ×								
2	2 🖹 🔹 🗘 🗘							
and a set of the set			Value					
Er			Car@18e88d					
	└─ <b>─</b> weigh	nt : kg	1800.0000					
	Snow Description							

The Requirement(s) table showing the constraint within a requirement which is not met and colored in red.

If you right-click on the Variables pane and select Export Value To > Instance, the variables will be evaluated and colored in red if there are constraint failures in the instance table, as shown in the following figure




The instance table showing the constraints after being exported to an Instance.

The status (pass/fail), related requirements, and instances for constraints are recorded using the **VerificationStatus** stereotype that is applied on the **Value** specification of the properties that you are working on. You can also see the detail of the constraint failure in the tooltip when hovering the mouse over any highlighted red values in the Requirement/Instance table as shown in the following figure

Bariables         ×         ○         Breakpoints         ×			
¢ ¥ ě	Ö -		
Name	Value		
□ □ Car {weight <= 1700.0, high <= 5.0}	Car@66714a		
… V high : meter	3.0000		
V weight : kg	1800.0000		
H" weighteneck - weight Venneauon (weig	weight vernication@090eco		

The simulation console showing the variables which have met or not met the constraints.

In addition, failed verdict of State Invariant is highlighted with red values and the tooltip. However, you must create a Dependency relation between the testcase and value property as shown in the following figure.



Failed State Invariant with highlighted red values and the tooltip.

If the VerificationStatus state on the Value specification fails, the active validation will be marked for notification with the fail status tag as shown in the following figure

Specification of Literal Real <> X						
Element tagged value spe Select a tag and click the Cre						
Image: Second state   Image: Second state	Tags         Profile: <all>         Imp Imp Imp Imp Imp Imp Imp Imp Imp Imp</all>	Property:    requirement : Class  Value  I Estimated mass [requirements]  I Estimated mass [requirements]				
	Close <u>B</u> ad	Eorward Help				


The Specification dialog showing verification status with the fail status tag.

The VerificationStatus stereotype, as shown in the figure above, has the tags as follows

Тад	Description		
constraint	The name of the failure constraint.		
requiremen t	The name of the failure Requirement.		
status	The result of the verification, either pass or fail.		
timestamp	The timestamp of the first failure recorded.		

## **Remember Failure Status option**

During the evaluation of particular configurations and scenarios, some Requirements/constraints can fail, and those values are marked in red. However, they may pass later and are marked in green again, but the failure is not recorded by default. To solve this problem, Simulation Toolkit provides the **Reme mber Failure Status** option in «SimulationConfig» to remember any failure status until the termination and record it as fail, even though it passes at the end. If the **Remember Failure Status** option is set true, and there are constraint failures during the simulation, the first fail status will be recorded in the status of «VerificationStatus» of new/recorded instance, and the time of the first failure will also be recorded in the **timestamp** tag as shown in the figure below.



Setting the Remember Failure Status tag of a SimulationConfig to record the fail status and timestamp if available.

#### **Related pages**

- Requirement Table
- Variables pane