

# Stereotype

A stereotype defines how an existing metaclass may be extended. It enables the use of a platform, a domain specific terminology, or a notation in place of, or in addition with, the ones used for the extended metaclass. Similar to a class, a stereotype may have properties which may be referred to as tag definitions. When a stereotype is applied to a model element, the values of the properties may be referred to as tagged values. A stereotype can extend any model element from the reference metamodel (any UML model element). For example in UML, States, Transitions, Activities, Use cases, Components, Attributes, Dependencies, etc. can all be extended with the stereotypes. The stereotypes are created as separate model elements and can be drawn in almost all diagrams. You can [specify stereotype properties](#) in the stereotype [Specification window](#). In the same window, you can find the description of each property. Descriptions are presented in the description area of the [Specification window](#).

Stereotype notation in diagrams use the guillemets instead of symbols « » (see the following figure). However, when editing elements in a diagram, you can still enter the stereotype names between the « » symbols.



The following procedures describe how to work with stereotypes:

- [Creating a stereotype](#)
- [Creating stereotype with an image](#)
- [Applying a stereotype](#)
- [Changing the stereotype's metaclass](#)
- [Displaying the stereotype icon instead of the shape on the diagram pane](#)
- [View assigned image properties](#)
- [Changing the order of the stereotypes](#)
- [Saving the stereotype information in XMI](#)
- [Changing the stereotype display mode](#)




## Creating a stereotype

To create a stereotype, do one of the following

- Open or create the [Profile Diagram](#). On the diagram [pallet](#), click the Stereotype button and place it on the diagram pane.
- In the Containment tree, select a Profile, and from the shortcut menu, select **Create Element > Stereotype**.


## Creating stereotype with an image

To create a stereotype with an image

1. In the stereotype's [Specification window](#), click the **Icon** specification cell to edit and select an [image you want to place](#) for the stereotype by selecting an image form:
  - the image library, click .
  - the file system, click .
  - using URL, click .
2. Select an image and click the **Open** button.
3. Close the Specification window.

## Applying a stereotype

To apply a stereotype, do one of the following:

- In the corresponding element's [Specification window](#), click the **Applied Stereotype** property specification cell, then click , and select stereotypes from the open list. After you have selected, click **Apply**.
- In the element's shortcut menu, select **Stereotype** and select a stereotype that you wish to apply. Click **Apply** when you are done.
- On the diagram pane, select an element and in that element's name area, type the stereotype name between brackets « ». The element's name comes after the stereotype.




If you want to name the element Books and assign it the «table» stereotype, in the element's name area type the following: «table» Books.

The name completion for the stereotypes works in the name editing mode, press **Ctrl+Spacebar** or **Ctrl+Backspace** to get a list of available stereotypes.

You can change the order of the stereotypes applied to the element. The symbol style of the first stereotype in the list will be applied to the element.


## Changing the stereotype's metaclass

To change the stereotype's metaclass

1. Do one of the following:
  - On a diagram pane, select the stereotype and from its smart manipulator toolbar, choose the **Metaclass** button.
  - In the stereotype's [Specification window](#), click the **Metaclass** specification value cell, and then click .
2. In the **Select Metaclass** list, select the metaclass you want to apply.
3. Click **Apply** when you are done.

## Displaying the stereotype icon instead of the shape on the diagram pane

To display the stereotype icon instead of the shape on the diagram pane

1. Select the shape on the diagram and click the [Compartment smart manipulator](#).
2. Click  to expand the menu and select **Suppress All**.

## View assigned image properties

To view assigned image properties

- In the stereotype [Specification window](#), right-click the **Icon** property specification cell and select **Open Specification**. The Image specification window opens wherein you can see and specify image properties.

## Changing the order of the stereotypes

If a symbol has several stereotypes applied, you can change the order of stereotypes for visual purposes.

To change the order of the stereotypes

1. Right-click the symbol to open the shortcut menu, click **Stereotype**. The **Select Stereotype** dialog opens.
2. Click the **Order** button. The **Order Stereotypes** dialog opens.
3. Select a stereotype and click **Up** or **Down** buttons to change the order of the stereotypes.

## Saving the stereotype information in XMI

You can choose the location of the applied stereotypes' information in the XMI file. Information can be saved at the end of the file or inside the element's information. By default, stereotype information is stored at the end of the XMI file.



### Storing Information

 store information inside an element

## Changing the stereotype display mode

From the main menu, select **Options > Environment**.







- The **Environment Options** dialog opens.

You can change the stereotype name and its icon visibility on an element's shape.

- In the **General** options group > **Save/Load**, set the **Save Stereotype Information within Element** to *true*.

To change the stereotype display mode on the element shape

1. Click the shape, and then, click buttons to [suppress all the compartments](#).
2. Click the shape and then click the [Compartments button](#). From the menu, click the **Stereotypes** and then select a desired display mode that are described in the following table:

Show Stereotypes Property Value	Shape	Icon of the stereotype on the shape	Name of the stereotype	Image of the stereotype instead of the element shape
Text and icon		displayed	displayed	-
Text		not displayed	displayed	-
Icon		displayed	not displayed	-
Shape Image and Text		-	displayed	displayed*
Shape Image		-	not displayed	displayed*
Do Not Display		not displayed	not displayed	-

\* To display the image of a stereotype instead of the element shape, all element compartments should be suppressed.

#### Related pages

- [Profile diagram](#)
- [Model Elements](#)
- [UML Profiling and DSL Guide](#)

#### Sample model

We recommend to analyze usage of stereotypes in the sample model *UML Extensions* that comes with MagicDraw. To open this sample do one of the following:

- Download [UML Extensions.mdzip](#).
- Find in modeling tool *<modeling tool installation directory>\samples\product features\UML Extensions.mdzip*.