
Global options for Code Engineering

Code Engineering Options for all Sets in your Project

Choose **Project** from the **Options** menu. The Project Options dialog box appears. You can set the Code Engineering options in the **Project Options** dialog. The **Project Options** dialog box has two main collections of customizable options, represented by the hierarchy tree on the left side of the dialog box. The figure below illustrates **Code Engineering** related options.



Code Engineering options in the Project Options dialog.

In the option list, select Code engineering and specify the following items:

Item name	Description	
Default Working Directory	Enter the name of your working directory.	
Default Working Package	Define any package for the reverse output or code generation. Your model will be reversed or the code will be generated from this specified package.	
Default Paths for References	Add specific profiles, used projects, or libraries to define where to search for paths for references during reverse/code generation.	
Default Encoding	Click to open a list of available encodings.	
Default language	When selected, the syntax checker of the selected language runs while Code Engineering is executed.	
Use Syntax Checker	When selected, the syntax checker runs while Code Engineering is executed.	

Directory for Temporal Files

You can specify Active Directory, System, or you can select another directory.

The following table describes other ${\bf Code\ Engineering\ }$ options:

Option	Element Name	Description
Code Generation		Set code generation options using the fields listed in the right side of the Project options dialog box. The Code generation area contains boxes with the same functionality as the Code generations options dialog box. See Generating Code.
Reverse		Set reverse options for all reverse actions of the project using the options listed on the right side of the Project options dialog box. The Reverse Options area contains boxes that have the same functionality as in the Reverse options dialog box.
Java Language Options Set the generated code style for Java programming anguages in the Default language field ound on the right side of the Project Options dialog box.	Generate opening bracket in new line	Opens a bracket in the new line being generated.
	Generate spaces	Generate spaces inside an assignment and other operators.
	Generate empty documentation	Comment brackets are placed in your code, unless class in the model has no documentation.
	Automatic "import" generation	Automatic generation of "import" sentences according to classes referenced in the generated class.
	Class count to generate import on demand	Specify the number of classes imported from a single package until all statements importing a single class are substituted with a statement importing an entire package.
	Documentation Processor	After selecting the Java Doc processor, click to open the Documentation Properties dialog box.
	Style	Two styles are available for documentation.
	Use CLASSPATH	The button is activated. Search a classpath for importing sentence generation in the Set classpath dialog box.
		∑ Set CLASSPATH
		lib/xalan.jar C:\Program Files\Java\jre1.8.0_144\jib\resources.jar C:\Program Files\Java\jre1.8.0_144\jib\rt.jar C:\Program Files\Java\jre1.8.0_144\jib\sunrsasign.jar
		C:\Program Files\Java\jre1.8.0_144\lib\jsse.jar C:\Program Files\Java\jre1.8.0_144\lib\jce.jar
		C:\Program Files\Java\jre1.8.0_144\jib\charsets.jar C:\Program Files\Java\jre1.8.0_144\jib\jfr.jar C:\Program Files\Java\jre1.8.0_144\classes
		Get from System
		OK Cancel Help
		Click Get from System to get the CLASSPATH variable defined by the operating system or click Add and select the classpath directory.

	Java Source	Available choices are 1.4, 5.0, 7.0, or 8.0.
	Header	Add a specific header to all your code files. Click and enter the header text in the Header dialog. You can also define \$DATE, \$AUTHOR, and \$TIME in the header.
C++ Language Options Set the generated code style for C++ programming languages.	Generate opening bracket in new line	Opens a bracket in the newly generated line.
	Generate spaces	Spaces inside an assignment and other operators are generated.
	Generate empty documentation	Comment brackets are placed in your code, unless the class in the model has no documentation.
	Generate methods body into class	Select check box to generate methods body into class.
	Generate field initialization into class	Generates the value initialization for the attribute.
	Automatically remove unnecessary usage relationship	Tracks the use of classes and removes the unnecessary include directives.
	Documentatio n Style	Four styles are available for documentation.
	Use include path	Click and then specify the path for the #include directives in the Set Include Path dialog box.
	Use explicit macros	Select the check box. The button is activated. Click it and use a set of predefined macros in the C++ Macros dialog box.
	Header	Add the specific header to all your code files. Click and enter the header text in the Header screen. You can also define \$DATE, \$AUTHOR, and \$TIME in the header.
CORBA IDL 3.0 language options	Generate documentation	Includes the documentation of an element in the comment.
	Generate opening bracket in new line	Opens a bracket in the newly generated line.
	Generate spaces	Spaces inside an assignment and other operators are generated.
	Generate empty documentatio n	Comment brackets are placed in your code, unless the class in the model has no documentation.
	Generate imports	Generation of "import" statements for classes referenced in the generated class.
	Generate preprocessor directives	Generates pre-processors directives.
	Generate end comments for composite elements	Generates end comments with composite element names.

	Generate operation parameters on the new line	Generates operation parameters on the new line.
	Documentatio n Style	Three styles are available for documentation.
	Header ""	Add the specific header to all your code files. Click and enter the header text in the Header dialog. You can also define \$DATE, \$AUTHOR, and \$TIME in the header. Since MagicDraw version 17.0, the variable \$DOCUMENTATION can be used to
		export the documentation of the file component (from the File View package) as a header of the IDL file.
		Functionality Availability variable \$DOCUMENTATION is available with MagicDraw 17.0 Service Pack 4 and later versions.
	Set Include Path	Specify the path for the #include directives. Click to open the Select Folder dialog box.
DDL Language Options	Generate opening bracket in new line	Opens a bracket in the newly generated line.
	Generate spaces	Spaces inside an assignment and other operators are generated.
	Generate documentatio n	Comment brackets are placed in your code, unless the class in the model has no documentation.
	Header	Add the specific header to all your code files. Click the button and enter header text in the Header dialog. You may also define \$DATE, \$AUTHOR, and \$TIME in the header.
C# Language Options	Generate opening bracket in new line	Opens a bracket in the newly generated line.
	Generate spaces	Generates spaces inside an assignment and other operators.
	Generate empty documentatio n	Comment brackets are placed in your code, unless the class in the model has no documentation.
	Generate required "using" directives	Automatic generation of "using" directives. This option facilitates the usage of namespaces and types defined in other namespaces.
	Concatenate namespace names	If not selected, namespace names are separated into several lines, e.g. namespace A
		namespace B
		{

Documentatio n: • Processor • Style	 Use C# XMI processor then generates c# xmi documentation for commenting the code. Select one of the three available documentation styles.
Header	Adds the specific header to all your code files. Click and type the header text in the Header dialog box. You can also define \$DATE, \$AUTHOR, and \$TIME in the header.
Conditional Symbols	Add the conditional symbols which cannot be recognized and should be skipped during reverse. Click the '' button and add conditional symbols in the Define Conditional Symbols dialog box.

Related Pages:

- Java Documentation Properties dialog box
 Round Trip
 Type Mapping Table

- Code Engineering Sets
 Generating Code
 Reverse Options
 Global options for Code Engineering
 Files of Properties
 Java Code Engineering
 C++ Code Engineering
 C# Code Engineering
 CORBA IDL Mapping To UML
 WSDL