



Auto-generating HTML files

When you start the Web Server option in your model's <<SimulationConfig>>, and **Start Web Server** is **true**, Cameo Simulation Toolkit will automatically generate HTML files from all used UI Configurations. This feature saves you a lot of time because you are not required to manually export them to get those HTML files. You can then use UI Mockups instead of local UI Mockups and control your model simulation on a web browser of any remote devices.




The Start Web Server Properties options in the <<SimulationConfig>> Specification window to auto-generate HTML files.

When the <<SimulationConfig>> is run, the build-in web server will start, HTML files with a hyperlink to each file in the local project folder will be generated, and a URL with a hyperlink will be shown in the simulation **Console** pane (regardless of the **Options** mode you are using in the **Console** pane).



The web server notification and URL in the simulation Console pane.

Clicking the URL will open the project(s) homepage in your web browser where you can view and control the simulation through the Web UI. To control the simulation through the web UI, you need to first [enable the Add Control panel](#) property option.



Simulation on the Web UI.

To run a model simulation on the Web Server


1. Double-click the <<SimulationConfig>> to open its Specification window.
2. Select **Web Server Properties** from the left-hand side pane and select the **Start Web Server** check box (**true**).
3. Click the URL in the **Console** pane to open a web-browser as the UI.



Important


- To prevent overwriting, HTML files will be not be regenerated if they have ever been generated before.
- The HTML files will be generated anew after you customize the files, e.g., add a logo or change the text color or size, using the same filename.
- You can delete or rename the existing HTML files if you need them to be regenerated.

Depending on the circumstances, you may want to manually generate HTML files for further customization of the web UI Mockups. Manually generating HTML files through a duplicate and diagram or HTML Support tool will be possible if using the **Generate HTML** command only once when the files are generated, a warning message box will open to prevent you from accidentally overwriting them. All generated HTML files will be written and stored in the project's working directory.



The Generate HTML button on the toolbar of the UI Modeling diagram.

To export a UI Modeling diagram from MagicDraw to HTML5

1. Double-click the UI Modeling diagram to open it.
2. Click . If the file already exists, a warning message box will appear. Otherwise, skip Step 3. A console message will show the information if the files were written successfully.
3. Click **Yes** to replace the existing files or **No** to cancel.

**Tip**

Anyone with access to the network the web server is on will be able to access the web link via a web-browser.

Sample model

The model used in the figures on this page is the **Calculator** sample model that comes with MagicDraw.

To open this sample, do either of the following

- Download [Calculator.mdzip](#).
- Find it in the modeling tool *<modeling tool installation directory>\samples\simulation\Calculator.mdzip*.

Related page

- [Simulation console](#)