
Checking changes and synchronizing

If you choose to check elements for changes before synchronizing them, you can select which changes should be synchronized and whether they are synchronized from a modeling tool to Teamcenter or vice versa.



Synchronization rules

- If new elements have been created, synchronizing will create corresponding elements in Teamcenter or a modeling tool depending on where these elements are missing.
- · If elements have been removed, synchronizing will remove corresponding elements from Teamcenter or a modeling tool depending on where To check elements for changes and synchronize them these elements still exist. Note that when you remove items from a Teamcenter (when synchronizing or otherwise), they are not completely
 - 1. Stafefett from Ting Too name by til the ସ୍ତେମ ହେନ୍ତି ଓ ନେ (Benediction of the changes and synchronize.
 - Connect to the Teamcenter server if a project has elements with changed properties, you can use the **Conflict Dashboard** dialog to select whether the changes are Do one of the following:
 - synahronized form the model tank the thorac entered of the constant of the contract of the con synchronize them.
 - b. In the Teamcenter Active Workspace panel, select the item you want to check for changes and/or synchronize (i.e., scope) and click
 - This option checks changes only for the selected item (e.g., a folder) and the items it owns, and allows to synchronize them. 4. In the Conflict Dashboard dialog (shown below), view the changes between the elements in your modeling tool and items in Teamcenter.
 - Display: All Changes iemens Teamcenter @ http://teamcenterdevel:8080/tc [Siemen... Car Climate Control [MagicDraw] Click to filter a □ 02 Logical Model a 02 Logical Model certain type □ 021 System Requirements ··· 🛅 021 System Requirements E- R CAR CC System Requirements PEO-000074/A+1-CAR CC System Requirem of changes Operating Modes v3
 System Performance --- 8 REQ-000075/A; 1-Operating Modes v3 - Air Distribution 🔧 002565/A; 1-Air Distribution Air - Communicatio - Communication - Electricity - Electricity Cooler you want to 🦫 002562/A; 1-Coole Commu synchronize Electricity






Tips for using Conflict Dashboard dialog, different types of changes are highlighted with different colors. The meaning of each color is

specified on the bottom of the dialog

- 5. If you have proceed interactive and have proceed interactive of the contractive of the process of the proces
- Select the check boxes next to the changes you want to synchronize. If you want to synchronize the changes from your modeling tool to Teamcenter, select the changes on the left side of the dialog (the modeling tool side). If you want to synchronize the changes from Teamcenter to the modeling tool, select the changes on the right side of the dialog (the Teamcenter side).
- 7. Click the Synchronize button.
- 8. When you're asked if you want to continue, click Yes.
- 9. Wait for the confirmation message indicating that synchronization is complete. Otherwise, move to the next step.
- 10. If the Synchronize New Node dialog opens, a new element you need to map is created during synchronization. Select the type of the new element and click Next.



- **11.** If needed, map the properties of the new element:
 - a. Click the Edit button.
 - **b.** On the left side of the **Synchronize New Node** dialog, find the source element property you want to map.
 - c. From the drop down list on the right side of the dialog, select the target element property you want to map to the source element property.
- 12. Click the Finish button to exit the Synchronize New Node dialog.

When you get a confirmation message, the synchronization is complete.

Related pages

- Importing data
- Exporting data
- Synchronizing without checking changes