

Migrating projects from Teamwork Server

- [Pre-conditions](#)
- [Actions before migration procedure](#)
- [Migration Procedure](#)
- [Troubleshooting](#)

The following instructions describe how to migrate projects from MagicDraw Teamwork Server to the Teamwork Cloud (TWCloud). These instructions cannot be applied to users' and permissions' migration. The users and permissions can be migrated only manually.

Pre-conditions

- Server, which you want to migrate from, and the server, which you want to migrate to, are connected to the same network (recommended).
- TWCloud repository has enough space on disc to store migrated projects. We recommend to allocate at least 100 MB per project.
- Client and TWCloud server versions are the same. For example, both 19.0.
- The user who performs the migration has the **Administer project** or **Read model** permission on Teamwork Server and the **Resource Creator** role on TWCloud.

Actions before migration procedure

1. Make a [back up](#) of the Teamwork Server repository.
2. Install a temporary Teamwork Server of the same version as the Teamwork Cloud.

 Please contact your sales executive for getting a temporal licence key.

3. Start the temporary Teamwork Server with the backup repository.
4. [Resave projects in this temporary Teamwork Server](#). After that, projects are ready to migrate to the Teamwork Cloud. This step is recommended for smoother and faster project migration to TWCloud.


Migration Procedure

1. [Log in to the temporary Teamwork Server](#).
2. From the **Collaborate** menu, select **Export Projects to TWCloud**. The **Project Export Wizard** opens.
3. Select the projects you want to migrate to TWCloud repository – in the **Action** column of each project, select one of the following:
 - **Export Trunk**, if you want export the last trunk version of that project.
 - **Export All Branches**, if you want to export the last trunk version of that project and the last versions of all its branches.
 - **Export Custom Branches**, if you want to export the last versions of selected branches and/or trunk of that project.

-  If you select a project that is already exported to TWCloud, it will be skipped. The project cannot be exported twice.
- To ensure project integrity, it is recommended to export all dependent projects (projects with its used projects) in one go.

 You want to export all the projects in the list, select **Export Trunk** or **Export All Branches** from the drop-down list on the toolbar above that list.

- After export is done, used projects will end up as separately embedded projects instead of being correctly linked. Thus,

4. Click **Next**.
 5. Type your u
 6. Click **Finish**
 7. Wait while p
- 

 Only the last versions of the selected projects are exported. Project history cannot be migrated.

8. Log out of T
9. [Log in to TWCloud](#).
10. From the **Collaborate** menu, select **Open Server Project**.
11. In the **Open Server Project** dialog, find the exported to TWCloud projects, open them, and perform [collaborative tasks](#).



Troubleshooting

Projects migration cannot be completed

The projects exported to TWCloud will have original commit details from the Teamwork Server:
This may happen because of many reasons, for example:

- Project has recovered elements
- Some profile/plugin is not installed
- The date of the last commit in the Teamwork Server
- Project elements are locked by other users (in case the project is of older format)

To get the thorough report of the last commit in the Teamwork Server
To get the thorough report of the particular issue, open the project and read the message that instantly appears on the project load. Fix the reported issue and try to export again.

These details can be found in the Version Properties dialog.
If the problem persists, report the issue with the log file attached to No Magic Customer Support team.

Project migration is terminated because of lack of memory

To solve this issue, increase the size of memory allocated for the client application, that is, MagicDraw, Cameo Systems Modeler, or other. For this, do the following:

1. Open for edit the *.properties* file of the client application, for example, *magicdraw.properties*, which can be found in *<MagicDraw installation directory>\bin*.
2. In the *JAVA_ARGS* line, replace *-Xmx800M* with *-Xmx3700M* , which stands for 3,7 GB allocated, or greater value.
3. Restart the client application.
4. Try to export again.

User rights are insufficient to create projects in TWCloud

To export projects to TWCloud you need to have the **Resource Creator** role. Contact the TWCloud Administrator to obtain this role.