## **Customizing Drag-and-Drop**

The drag-and-drop customization allows you to create relationships or assign property values by dragging and dropping one element onto another right in the diagram pane. By using the DSL engine, you may set up your own drag-and-drop specifications between elements:

- create relationships
- assign property values

There are a number of predefined rules to create relationships or assign property values automatically.



• drag-and-drop one element from the diagram pane onto another element on the diagram pane

Below is a list and through the stream of th

Property drag-a	nd-drop two or more elements from the Model Browser onto an element on the diagram pane  Description
Source Element	Specify the element type to drag to the target element. Specify a class, metaclass, or stereotype.
	This is a mandatory property: if the <b>Source Element</b> property is undefined, then the drag-and-drop rule is inactive.
Representatio n Text	Specify the name of the drag-and-drop rule.
Relation Action Result	Specify a relationship created between the source and target elements after drag-and-drop.
Property Action Result	Specify a property assigned to the target element after drag-and-drop.
	Note. Before specifying this property, you need to add the drag-and-drop rule into the target element customization Specification window > Connection Rules category > Allowed Drag And Drops property.
Append Mode	Change the append mode for the property assignment. The possible <b>Append Mode</b> property value is <i>true</i> or <i>false</i> .
	If true, properties are assigned one by one. If false, the created property overwrites the former property.