# Activity simulation engine

On this page

- fUML engine settings
- ReadLine support
- Guards in Swimlanes

Magic Model Analyst provides an Activity simulation engine that allows you to run an Activity Simulation on Activity diagrams or Activity Elements. Magic Model Analyst also includes the implementation of OMG Semantics of a Foundational Subset for Executable UML Models (fUML), an executable subset of standard UML, that can be used to define the structural and Behavioral semantics of systems. fUML defines a basic virtual machine for the Unified Modeling Language and supports specific abstractions enabling compliant models to be transformed into various executable forms for verification, integration, and deployment.

Various UML Activity diagram concepts are supported, including Object and Control Flows, Behavior and Operation Calls, sending Signals via Connectors with or without Ports in Internal Structure, accepting Signals and Time Events, Pins, Parameters, Decisions, Structured Activity Nodes, and many more.

The Activity simulation engine features include the following

- fUML 1.3 specification support.
- Any Action languages in opaqueBehaviors, opaqueExpressions, Decisions, Guards, and Constraints (see Integration with MATLAB® for more details).
- CallBehaviorAction with nested diagrams simulation and animation.
- SendSignalAction to send a Signal to a global Event queue to be used by the system level but not by the subsystem, e.g., in State Machine.

/!∖ Note SendSignalAction has the Target input Pin for specifying the signal receiver. If this Pin is omitted, the signal instance will be sent to

the context itself.

- CallOperation Action through a Port. Sending Signals through a Port.
- Support for Decision Nodes with probabilities over all outgoing edges.
- Support for Decision Nodes with a Decision input that provides input to Guard specifications on outgoing edges from each Decision Node.



Note ∕!∖

· You can simulate only Activities that are owned by a Package or a Class. As a workaround, the CallBehavior Actions, owned by the Call

Behaviors in a Package, will be used for the entry/do/exit Behaviors in States.

Most of the Firm Constant and Conjecting and Constant and

- CotherOppertFlow during simulation.
- Object Flow (Transformation is not supported)
- Input Pin (Illegal type is not supported)
- Output Pin
- Activity Final Node
- FlortFange Noderegular UML (Boolean expression)
  Activity Parameter Node: The parameter of the Activity Parameter Node must be defined. If the Activity Parameter Node violates the rule,
- Simulation will print a warning message in the Console pane.
- Decision Node
- MaggetModeain menu, click Options > Project and select Simulation on the left of the Project Options dialog.
- Join Node
   200 Hotel
   200 Hotel
   400 Hotel
- Structured Activity Node
- Conditional Node
- Loop Node: the setup part will not be executed as the fUML specification. The number of Input Pins of the Loop Node must be equal to Output Pins. If the Loop Node violates the rule, Simulation will print an error message in the Console pane.
- ExpanishizidRegibre can be passed as a parameter of Behavior of an opaque expression through a pin of Action. If a valid return value is from an Expansion Node
- Objectioned Behavior of a Guard, the body of the Guard will be ignored. However, if the Behavior is <unspecified>, the body of the Guard will be • Central Buffer Node Used Data Store Node
- Actions
  - AcceptEventAction •
  - AddStructuralFeatureValueAction
  - CallBehaviorAction
  - CallOperationAction
  - ClearAssociationAction
  - ClearStructuralFeatureAction
  - CreateLinkAction
  - CreateObjectAction
  - DestroyLinkAction
  - DestroyObjectAction
  - OpaqueAction
  - ReadExtentAction
  - ReadIsClassifiedObjectAction
  - ReadLinkAction
  - ReadSelfAction
  - ReadStructuralFeatureAction
  - ReclassifyObjectAction
  - ReduceAction
  - RemoveStructuralFeatureValueAction
  - SendSignalAction
  - StartObjectBehaviorAction
  - TestIdentityAction
  - ValueSpecificationAction

#### fUML engine settings

You can customize Behaviors of the fUML engine for Simulation to match your project Requirements through the Project Options dialog as shown below.

To customize the fUML engine settings in the Project options dialog

- 1. On the main menu, click Options and select Project. The Project options dialog opens.
- 2. On the left pane, click General > Simulation.

3. Go to the **fUML Engine** group and set any of the properties as desired.

V Project Options Specify general project properties Specify the validation, project depend	ency checker options and other general project-specific options.		Magnetakod soki Sistingariakod soki Sistingariakod Gonestrank
<b>Q</b> Type here to filter options	Simulation		
Image: Second Secon	Image: Image	<ul> <li>✓ true</li> <li>false</li> <li>✓ true</li> <li>Ø true</li> </ul>	
		I OK	Reset to Defaults

The following table describes the project options of the fUML engine.

Property	Function	
Use fUML Decision semantics	If set to <i>true</i> (false by default when in the UML mode), all Guards will be solved to true when the flowing token value matches the Guard value (instead of evaluating every Guard as Boolean operation).	
Auto Create fUML Object of Output	If set to <i>true</i> , automatically create an fUML object of output.	
Pass Caller Context	If set to <i>true</i> , pass the caller context to the called Behavior if it does not have its own context specified. Otherwise, use the Behavior itself as context.	
Terminate Nested Behaviors	If set to true, terminate nested Part Behaviors if their parent object Behavior is terminated.	
Terminate Streaming Behaviors by Output Parameter Multiplicity	If set to <i>true</i> , a streaming Activity terminates when each of its output parameters receives a cumulative number of values equal to the upper bound of the parameter multiplicity. If set to <i>false</i> , a streaming Activity terminates only when forced by the Activity final node or termination of the Activity that invoked it.	
Allow Concurrent Allocated Activities	If set to <i>true</i> , Activities can be executed in parallel even if the allocated resource is busy. If set to <i>false</i> , only one allocated Activity is executed for an object represented in an Activity Partition.	
	Allow Concurrent Allocated Activities option is set to <i>true</i> , it is recommended to use a time event to control the execution of parallel activities. A time event will increase the simulation performance in case one parallelly executed activity needs to get a response from another in order to start.	
Note can instantiate a nested composite structure using the standard PSCS construction mechanism by default.		

## **ReadLine support**

ReadLine is a function that allows the user to enter value through the input line on the **Console** pane. A Call Behavior Action can be set Behavior as **Read** Line [fUML\_Library::BasicInputOutput] using fUML\_Library.mdzip from the Use Project dialog. Before using the ReadLine function, you need to include fUML\_Library.mdzip in the project first. 1. Click File > Use Project > Use Local Project from the main menu to open the Use Project dialog.

这 Use Project	>		
Select a project to use Select a project from the file syst Predefined locations help finding o	em or predefined location (paths to used projects) and click 'Next' to proceed. default application profiles and libraries.		
1. Select project	Select a project to use		
	◯ From file system		
	From predefined location		
	Paths to used projects:		
	<pre><pre><pre><pre><pre><pre><pre><pre></pre></pre></pre></pre></pre></pre></pre></pre>		
	<install.root>\profiles</install.root>		
	<install.root>\modelLibraries \<install.root>\modelLibraries</install.root></install.root>		
	C:\Program Files (x86)\MagicDraw\modelLibraries		
	Project description:		
	< Back Next > Finish Cancel Help		

2. In the Select a project to use area, select the From predefined location option.

3. In the Paths to used projects list, select <install.root>\modelLibraries.

4. In the directory tree list, select **fUML-Library** and click **Next>** to proceed to the next step.

🔯 Use Project				>	
Specify project usage options Specify usage options for the selected project and then click 'Finish' to start using it.					
<ul> <li>1. Select project</li> <li>2. Specify usage options</li> </ul>	Accessibility  Read-only  Read-write		Load Mode     Always load     Autoload     Autoload     Autoload with prompt     Manual load		
	Packages:				
	Shared Package	Preferred P	ath	Mounted On	
	FUML_Library				
		< Back	Next > Finis	sh Cancel Help	

5. You will be at the **Specify usage options** step. Click **Finish**. The **Question** dialog opens to ask you about showing auxiliary resources in the Containment tree. Click **Yes**.

🖹 Question		×
Auxiliary resources from used read-only projects are hidden in the Containment tree. Show auxiliary resources?		
Show this message next time Yes No Help		

Then a Call Behavior Action can now be set Behavior as a ReadLine Element. The ReadLine Element will be shown with two default Pins, i.e., result and errorStatus. During the simulation, the ReadLine Element is executed to allow entering value through the input line on the **Console** pane. The result of the ReadLine Element can be used by other Elements with any proper data types, e.g., Guard, as in the following figure



ReadLine support allows entering value through the input line on the Console pane.

### **Guards in Swimlanes**

Simulation supports Guards in Swimlanes in the Activity diagram as shown in the figure below. See also Using Guards on Transitions and Swimlane.



Guards in Swimlanes are supported in the Activity diagram.

#### **Related pages**

- Decision and Merge
- Behavior
- Action