

# Common Access Card

On this page:

- [Basic Configuration](#)
- [Configure username](#)
- [Configure the value displayed in the login button](#)
- [TrustStore Configuration](#)
- [Certificate Revocation List](#)

## Basic Configuration

In order for Common Access Card (CAC) authentication to work, SSL must be enabled on the authentication server:

```
server.ssl.enabled=true
```

Next, you need to enable certificate authentication:

```
authentication.certificate.enabled=true
```

The next step is to configure which part of the subject DN (distinguished name) will be used as the username (**authentication.certificate.username.template**), and which part will be displayed in the login screen (**authentication.certificate.displayname.template**).

Both of these values default to using (CN)



## Configure username

```
authentication.certificate.username.template=(CN)
```

The template can contain ASCII characters as well as placeholders in parenthesis that are replaced with relative distinguished name (RDN) values from the DN (if the username is constructed from the Subject Distinguished Name) or SAN (if the username is constructed from the Subject Alternative Name).

For example, when the subject DN or SAN (of type 4) on the certificate is CN=JohnDoe,O=MyCompany,C=GB:

Template: *(CN)*, username: *JohnDoe*

Template: *(O)-(CN)*, username: *MyCompany-JohnDoe*

Template: *CERT\_(CN)*, username: *CERT\_JohnDoe*

## Configure the value displayed in the login button

To configure the value displayed in the login button, we must edit the **authentication.certificate.displayname.template** property.

```
authentication.certificate.displayname.template=(CN)
```

For example, as shown in the picture above, when the subject DN or SAN (of type 4) on the certificate is *CN=JohnDoe,O=MyCompany,C=GB*, and the display template is *(CN) CERTIFICATE*, the button will display „JOHNDOE CERTIFICATE“.

For a list of all the advanced properties available for configuration, please refer to [Authentication by certificate](#).

## TrustStore Configuration

CAC integration requires that a truststore containing the Certificate Authority (CA) certificates that issue the user's certificates would exist. This truststore by default can be found under *AuthServer/config/*.

The following parameter properties need to be configured:

```
server.ssl.trust-store=config/truststore.jks
server.ssl.trust-store-type=JKS
server.ssl.trust-store-password=secret
server.ssl.client-auth=want
```

In a directory, named truststore, under *AuthServer/config/* place all the CA certificates. Upon startup of the authentication server, if **truststore.jks** does not exist, it will be created by importing the CA certificates located in *Authserver/config/truststore*. If you make changes to the certificates in the truststore directory, delete **truststore.jks** and restart the authentication service. This will recreate the truststore with the current set of CA certificates.

For a list of all the advanced properties available for configuration, please refer to [General parameters](#).

## Certificate Revocation List

The authentication server supports 2 methods of handling certificate revocation lists - via a URL, or via a local list stored in the file system. To enable this feature, uncomment either **authentication.certificate.revocation.list.url** or **authentication.certificate.revocation.list.file**, and point it to the location of the revocation list.

```
authentication.certificate.revocation.list.url=http://someserver.somedomain.com/revocation.lst
authentication.certificate.revocation.list.file=install_root/revovcation.lst
```

### Related pages

- [Authentication by certificate](#)