Cameo Business Modeler Plugin licensing

On this page

- Adding the license key file
- Activating at nomagic.com
- Obtaining the floating license

Adding the license key file

1. In the **Resource Plugin Manager** dialog, click the **Manage Licenses** button.
2. In the modeling tool **License Manager** dialog, click the **Select License Key Files** button. Then in the **Select Key File** dialog, select the license key file and click **Open**.
3. In the **License Configuration** dialog, check the license information and click **OK**.
4. When you receive the message to restart the modeling tool, click **OK**.
5. Restart the modeling tool.

Activating at nomagic.com

Before starting the plugin license activation, make sure plugins are installed.

1. Log in at nomagic.com as license owner.
2. At the right side of the webpage, under **Members**, click **License Activation Management**.
3. In the **License Activation Management** page, click the **Click to Edit** button to edit the record of the modeling tool for which you want to activate plugins.

4. In the **Edit license activation record** dialog, select the plugins you want to activate.



- If you want to activate the license for the **SysML Plugin bundle**, you must add both commercial plugins included in that bundle to the activation record: SysML Plugin and Cameo Requirements Modeler Plugin.
- If you want to activate license for **UPDM 2 Plugin bundle**, you must add all commercial plugins included in that bundle to the activation record: UPDM 2 Plugin, SysML Plugin, and Cameo Requirements Modeler Plugin.

5. Click **Save** when finished. The activation record is updated.
6. In the **Activation Records** table, in the **Get key** column, click the *Send* button to receive the license key by email or click the *Download* button to save the key locally.
7. Add the license key and restart the modeling tool.

Obtaining the floating license

- Make sure your floating license server contains the plugin license.
- Make sure the plugins are installed.

1. Start the modeling tool.
2. On the **Help** menu, click **License Manager**.
3. In the modeling tool **License Manager** dialog, click the **Use Floating License** button.

4. In the **FLEXnet License Server Connection** dialog, enter server name and port and click **OK.**

   Your system administrator provides the server name and port.

5. In the **Select Edition/Plugin** dialog, select edition and plugins and click **OK**.

If the **Automatically login each time <modeling tool> is started** check box is selected, the **FLEXnet License Server Connection** dialog will not be displayed and the licenses will be obtained automatically. If you need to reset the licenses or select additional ones, do the following:

1. In the main menu, click Options > Environment. The **Environment Options** dialog opens.
2. In the **Floating** options group, set the **Auto login to FLEXnet License Server** option to *false*.
3. Restart the modeling tool.