


Installing plugins

Choose one of the following ways to install a plugin in a modeling tool:

- Install a plugin bundle (.rdzip) that comes with a modeling tool directly via the **Resource/Plugin Manager** dialog.
- Install an individually purchased archived plugin file (.zip) via the **Resource/Plugin Manager** dialog.
- Install a plugin manually
- Obtain and install a plugin from a web server

To install a plugin bundle (.rdzip) via the **Resource/Plugin Manager** dialog

1. Start your modeling tool.
2. From the modeling tool main menu, select **Help > Resource/Plugin Manager**.
3. Click the  button.
4. In the **Manage Resource Locations** dialog, click **Add**. The **Select Resource Location or Distribution File** dialog opens.
5. Specify the location of a plugin bundle (.rdzip) file and click **Open**. The resource location is added.
6. Click **OK** to import resources.



You can extract the .rdzip file and then [add selected plugins individually](#).

To install an individual plugin from an archive file (.zip) via the **Resource/Plugin Manager** dialog


1. Start your modeling tool.
2. From the main menu of a modeling tool, select **Help > Resource/Plugin Manager**.
3. Click the **Import** button and specify the location of an archived plugin file (.zip) and click **Open**. The plugin is extracted and installed automatically.
4. Restart your modeling tool.

To install a plugin manually


1. Extract an archived plugin file (.zip) file to the same directory where your modeling tool is installed.
2. Start the modeling tool. The plugin is applied to your modeling tool.

You can also obtain the needed resources from a web server if you do not have the .rdzip file but have been provided with an URL by your license manager.

To specify the server where the resources and their descriptor file are located

1. Open **Resource/Plugin Manager** and click .
2. In the **Manage Resource Locations** dialog, click **Add URL**. The **Resource Server URL** dialog opens.

3. In the open **Resource Server URL** dialog, type or paste the server address.



4. Click **OK**.

The resources from the selected location are listed in the **Resource/Plugin Manager**.

For more information on managing resources, please see [Resource Manager](#).



Getting help

If you run into any installation related problems, try the following:

- checking the [FAQ section](#) for known problems
- checking the [No Magic Community forum](#)
- contacting [customer support](#)

Related pages

- [Modeling tools and plugins licensing](#)
- [FlexNet license server installation and licensing](#)
- [Installation and licensing](#)