

Licensing information

On this page

- [License types](#)
- [New installation \(no existing license server\)](#)
- [Checking which license is in use](#)
- [Specifying which license should be used](#)
- [Resetting a license](#)
- [License access configuration](#)

License types

You can purchase the following types of Cameo Collaborator for Teamwork licenses, depending on the number of connections you want to use:

License types	Authenticated commenting	Anonymous commenting	Number of concurrent authenticated connections	Access to content shared for anonymous use*	Predefined portals	Customized portals
5-connection license	+	-	5	Unlimited	+	+
10-connection license	+	-	10	Unlimited	+	+
25-connection license	+	-	25	Unlimited	+	+
50-connection license	+	-	50	Unlimited	+	+
75-connection license	+	-	75	Unlimited	+	+
100-connection license	+	-	100	Unlimited	+	+
Unlimited license	+	+	Unlimited	Unlimited	+	+

* Unauthenticated users can open Cameo Collaborator documents via [public links](#).

New installation (no existing license server)

Cameo Collaborator for Teamwork Cloud uses a floating license, managed by the FlexNet license server. The FlexNet license server information is specified when installing Cameo Collaborator for Teamwork Cloud, so make sure that you install the FlexNet server before installing Cameo Collaborator. Follow the steps below to apply the Cameo Collaborator for Teamwork Cloud license and start using the product.

To apply the Cameo Collaborator for Teamwork Cloud license

1. [Install and start the FlexNet license server.](#)
2. [Check if the FlexNet server is running.](#)
3. [Add the Cameo Collaborator for Teamwork Cloud license to the FlexNet server.](#)
4. [Install Cameo Collaborator for Teamwork Cloud](#) and specify The FlexNet server details during the installation.

Cameo Collaborator is ready to use once you apply the license. Note that you can change the FlexNet license server details later if needed.



Working with multiple licenses

The FlexNet license server can contain only one license. If you want to add multiple licenses to the same FlexNet license server (e.g., Cameo Collaborator, Teamwork Cloud, and MagicDraw), contact your sales executive and ask them to merge the licenses.

Checking which license is in use

You can check Cameo Collaborator for Teamwork Cloud license information, as described below.

To check the license information

1. In your internet browser, go to `http(s)://<domain_name>:<port>/resources` to open the Resources app.

 **Default port**
Cameo Collaborator for TWC uses port 8443 by default.

2. When the authentication page opens, sign in using your credentials.
3. In the same internet browser, go to `http(s)://<domain_name>:<port>/collaborator/api/collaborator/license/info`

The web page displays Cameo Collaborator license details, including the number of connections and expiration date.

Specifying which license should be used

If there are several licenses in the FlexNet server, you can specify which Cameo Collaborator license (edition) should be used.

To specify which license should be used

1. Go to the `<wap_installation_directory>\apache-tomcat\shared\conf` directory.
2. Open the `webappplatform.properties` file.
3. In the file, add the following property with the desired value (the value example below is for an unlimited license):

```
cc.floating.edition=100+ Connections
```

 **Valid property values**
The valid values for the `cc.floating.edition` property are:

- Demo Connections
4. Save and close the file.
 5. Restart the Web Application Platform.

- 10 Connections

Resetting a license

- 25 Connections

The instructions below explain how to reset the Cameo Collaborator for Teamwork Cloud license if, for example, the connection with the FlexNet server was lost.

- 50 Connections

- 75 Connections

- 100 Connections

To reset the Cameo Collaborator for Teamwork Cloud license

1. In an internet browser, go to `http(s)://<domain_name>:<port>/resources` to open the Resources app.

 **Default port**
Cameo Collaborator for TWC uses port 8443 by default.

2. When the authentication page opens, sign in using your credentials.
3. In the same internet browser, go to `http(s)://<domain_name>:<port>/collaborator/api/collaborator/license/reset`

Following a successful license reset, the open web page will display this message:

```
{"initialized":true}
```

License access configuration

After installing Teamwork Cloud and/or Web Application Platform, configure the FlexNet license server licenses in the `webappplatform.properties` file. This step is required to access the Cameo Collaborator license.

To change the FlexNet license server details

1. Go to the Web Application Platform configuration directory:

- Web Application Platform installation: `<WAP_installation_directory>\apache-tomcat\shared\conf`
 - Teamwork Cloud installation: `<TWC_installation_directory>\WebAppPlatform\shared\conf`
2. Open the `webappplatform.properties` file.
 3. Change the values of the following properties:
 - `flexnet.server.name`
 - `flexnet.server.port` (if different from the default port 1101)
 4. Save and close the file.
 5. [Restart Web Application Platform](#).