


# DH Links panel shortcut menu and Sync Status icons


You can right-click an item in the table in the **DH Links** panel to open a shortcut menu. This shortcut menu allows you to execute specific operations on a node in the panel.



The Shortcut menu in the table in the DH Links panel.

The table below explains the functions of the **DH Links** panel shortcut menu.

Command	Function
Select <i>MagicDraw project name</i> node in Application	Selects the element in the MagicDraw Containment tree.
Select <i>MagicDraw project name</i> node in DataHub Explorer	Selects the MagicDraw node in <b>DataHub/Alias Explorer</b> .
Select <i>Data Source name</i> node in Application	Selects the node in the original application, e.g., the node originally from DOORS will be opened in the DOORS client application.
Select <i>Data Source name</i> node in DataHub Explorer	Selects the node from other Data Sources, e.g., DOORS, in <b>DataHub/Alias Explorer</b> .
Change Direction (only for root nodes)	Changes the current direction of synchronization: <b>Two-way Sync</b> , <b>Sync from MagicDraw</b> , and <b>Sync to MagicDraw</b> .


View Schema Map	<p>Opens the <a href="#">View Schema Map</a> dialog.</p>  <p>The View Schema Map dialog.</p>
Exclude Node (not for root nodes)	Skips the synchronization of the selected node and its child nodes.
Include Node	Includes the selected node and its child nodes for the synchronization.
Update Pending DHLink (for Pending Update items)	Synchronizes the node by updating the pending DHLink.
Discard Update (for Pending Delete items)	Synchronizes the node by discarding the DHLink.
Remove DHLink	Removes the selected DHLink.



#### Note






- DataHub cannot recreate a node if its parent does not exist.
- You can perform the **Change Direction** and **Remove DHLink** command(sync relation) on a root node only.

You can click the **Sync Status** icons to filter the status of synchronization of the nodes. The **DH Links** panel displays only the DHLinks with the Sync status you have selected from the specified **Sync Status** icons.



The Sync Status icons on the DH Links panel.

All the **Sync Status** icons are listed in the following table

Button	Color sync	Status	Meaning
	Green	Synchronized	Displays only the DHLink of the <b>Synchronized</b> status.
	Blue	Orphan	Displays only the DHLink of the <b>Orphan</b> status.
	Red	Pending Delete	Displays only the DHLink of the <b>Pending Delete</b> status.
	Yellow	Pending Update	Displays only the DHLink of the <b>Pending Update</b> status.
	Grey	Excluded	Displays only the DHLink of the <b>Excluded</b> status.