

# Determining the Host ID

On this page


- [Determine host ID using GUI](#)
- [Determine Host ID when working with the no GUI Teamwork Server](#)

## Determine host ID using GUI

To determine the [Host ID](#) of the machine on which the Teamwork Server is installed

1. Start the Teamwork Server.
2. When the **License Manager** dialog opens, copy the text from the **Host ID** box.

 In case of multiple network adapters, the Host ID is encrypted.



 Do not close the dialog boxes. You will return to add the activated license key (see [Adding the license to Teamwork Server](#)).

## Determine Host ID when working with the no GUI Teamwork Server

Running the `teamwork_server_nogui` for the first time, you get this window:

```
Select C:\Users\agnpal\Downloads\MagicDraw_185_teamwork_server_no_install (1)\bin\teamwork_server_nog...
any kind whatsoever shall in any way modify or expand the terms of this Agreement. In the
event of any conflict or inconsistency between the terms of this Agreement and any documenta
tion, this Agreement shall preempt such documentation to the extent inconsistent.

Should you have any questions concerning this Agreement You may contact:

No Magic, Inc.
Legal Department
One Allen Center
700 Central Expressway South, Suite 110
Allen, Texas 75013 USA
Main: +1-214-291-9100
Fax: +1-214-291-9099

Software and Software Documentation (C) No Magic, Inc. 1998-2017. All rights reserved.
If You agree please type 'I agree': I agree
-----
In order to download a commercial license key file locked to a particular machine, please do
the following:
  1. Copy the Host ID that is shown in this message.
  2. Login to the license owner's account at http://www.nomagic.com/products/magicdraw.html
and select the License Activation Management menu item on the right side of the main page.
  3. Create a new offline activation record according to the instructions provided.
  4. Choose to either Download or Send the license key file from the record you create.
Note: Host ID is not needed for evaluation or commercial with expiration license.
Host ID: 0022dddd2222
-----
Enter the path to Teamwork Server 18.5 Unlock Key file :
```

Please use the host id printed on your screen.

#### Related pages

- [Activating a license](#)
- [Adding the license to Teamwork Server](#)
- [Activating the Teamwork Server commercial license](#)