

Group type mapping

The default mapping type in DataHub is group type mapping. If you prefer mapping node types to mapping the nodes one-by-one before copying and/or synchronizing them, you can select the **Group Type Mapping** mode from the **Mapping Mode** drop-down list. It arranges all nodes according to their types to allow you to see the grouped types instead of individual nodes arranged in a tree structure. You can select a type from the source tree and map it to another type in the target tree.



Note

Each formal module in DOORS is categorized as one node type.

Copy Data with Sync

Copy Data with Sync

Select all unmapped target types from the list and resolve them by defining the schema map. DataHub will create the DHLinks to maintain the nodes in the scope hierarchy.

Sync Direction:
☐ Two-way Sync
☒ One-way Sync from MagicDraw
☐ One-way Sync to MagicDraw

Mapping Mode:
Group Type Mapping

IBM Rational DOORS Next Generation Side

Folder::/JKE Banking (Requirements Management)
Term::/JKE Banking (Requirements Management)

☐ Exclude all non-mapped nodes from DHLinks.
☐ Define Target Type from Attribute Value

Attribute:
Created On

Default	Priority	Value	Target

MagicDraw Side

class

Class
ClassifierTemplateParameter
ReadIsClassifiedObjectAction
ReclassifyObjectAction
StartClassifierBehaviorAction
Customization
Drag&Drop Specification
Legend

☐ Set as default target type

Select Attribute to Sync

	Term::/JKE Banking (Requir...	Class [MagicDraw::JAR File ...	Conversion Rule
<input type="checkbox"/>	Alternative Spelling		
<input type="checkbox"/>	Contributor(Readonly)		
<input type="checkbox"/>	Created On(Readonly)		
<input type="checkbox"/>	Creator(Readonly)		
<input type="checkbox"/>	Description		
<input type="checkbox"/>	Identifier(Readonly)		
<input type="checkbox"/>	Modified On(Readonly)		
<input type="checkbox"/>	Parent(Readonly)		
<input type="checkbox"/>	Primary Text		
<input type="checkbox"/>	Service Provider(Readonly)		
<input type="checkbox"/>	Status		
<input type="checkbox"/>	Title		

Edit

OK
Cancel

Group type mapping mode in the Copy Data with Sync dialog.