

Starting and stopping Teamwork Server

You can choose to start and stop your Teamwork Server instance either from the Graphical User Interface (GUI) or the terminal console (required for headless UNIX/Linux installations), using the no GUI file. Choose the startup instructions below according to your operating system.

- [Starting/Stopping the Teamwork Server using a GUI](#)
- [Starting/Stopping the Teamwork Server without a GUI](#)

Starting/Stopping a Teamwork Server instance with a GUI

Starting Teamwork Server instance with a GUI



Note

To keep the Teamwork Server session running, add the Teamwork Server as a service. To add the Teamwork Server as a service, [learn here](#).

Windows

1. Do one of the following:
 - On the Windows taskbar, click **Start**, and select *MagicDraw Teamwork Server* from the program list.
 - Open *MagicDraw Teamwork Server installation\bin* and double-click the *teamwork_server.exe* file.



We recommend starting the Teamwork Server as an administrator. Right click the *teamwork_server.exe* file. Select **Run as administrator** from the shortcut menu.

2. In the **Import Configuration** dialog, do one of the following:
 - If you want to import environment options from an earlier Teamwork Server version, select the location and click **Import**.
 - If you want to use the default options, click **Use Default**.
3. Click the **Start Teamwork Server** button.

The Teamwork Server default port is 1100. If you want to change the port, do the following:

1. Run *teamwork_server.exe* in the server bin folder. The **Teamwork Server** startup dialog opens.
2. Click the **Change Server Port** button and enter the new server port. This port is used when launching the server, or when adding the Windows service.

The Teamwork Server exports remote objects only through the RMI registry port.

MAC OS

1. Open the *Application / MagicDraw Teamwork Server* installation folder and double-click the *MagicDraw Teamwork Server.app* file.
2. Click the **Start Teamwork Server** button.

UNIX

1. Open the *MagicDraw Teamwork Server installation/bin* folder and double-click the *teamwork_server* file.
2. Click the **Start Teamwork Server** button.

Stopping a Teamwork Server instance with a GUI

Windows

- In the *<Teamwork Server installation>/bin* folder, double click the *stop_teamwork_server.exe*.

MAC OS

- In the *<Teamwork Server installation>/bin* folder, double click the *stop_teamwork_server.app*.

UNIX

- In the command line, type the following command:

```
service teamwork stop
```

Starting/Stopping a Teamwork Server instance with no GUI

If you do not have a graphical user interface such as a Linux/Unix server or Windows server, you can launch Teamwork Server using the No GUI option. Choose the startup/stop instructions below according to your operating system.



Note

To keep the Teamwork Server session running, add the Teamwork Server as a service. To add the Teamwork Server as a service, [learn here](#).

Starting Teamwork server with no GUI

Windows

- From PowerShell or the command terminal run:

```
$teamwork_install_dir/bin/teamwork_server_nogui.exe
```

Linux/Unix/MacOS

- From the terminal run:

```
$teamwork_install_dir/bin/teamwork_server_nogui
```

- Follow instructions to verify your license (if needed)

Stopping Teamwork Server with no GUI

Windows

- From PowerShell or the command terminal run:

```
$teamwork_install_dir/bin/stop_teamwork_server.exe
```

MacOSX

- In the command line, type the following command:

```
$teamwork_install_dir/bin/stop_teamwork_server.app
```

Linux/Unix

- In the command line, type the following command:

```
service teamwork stop
```

Now you should be able to start working with your Teamwork Server successfully.

If you run into any further problems with installation, please try:

- checking the [FAQ section](#) for the known problems
- checking the [No Magic Community forum](#)
- contacting the customer support at support@nomagic.com

More information about working with Teamwork Server

If you need more information than provided on this page, read the following pages to learn about adding or removing Teamwork Server as a service, moving, updating, upgrading, or uninstalling Teamwork Server, and installing the Administrator Console.

- [Adding and removing Teamwork Server as service](#)
- [Moving Teamwork Server and license to another machine](#)
- [Updating or upgrading Teamwork Server](#)
- [Uninstalling Teamwork Server](#)
- [Teamwork Server Administrator Console installation](#)