

Activating a license

To activate the license at nomagic.com

- 1. Log in at nomagic.com as a license owner.
- 2. On the right side of the webpage, under **Members**, click **License Activation Management**.
- 3. In the **License Activation Management** page, click the **Create New License Activation Record** button.

LICENSE ACTIVATION MANAGEMENT (#524251)

The **License Activation Management** screen is dedicated for licenses activation, deactivation, license key files request, activation records review, and other license management activities.

In order to create activation record, click the **Create New License Activation Record** button and then enter user details, Host ID of the machine, and select products licenses, which will be activated for this machine.

Activation and License Activation Management screen [usage instructions](#).

Installations status filter:

Activated

☒ Enable license select during online activation

Profile ID	First Name	Last Name	Email	Date	Host Id	Installation status	Activated products	Get key	Personal comment
No records.									

Create New License Activation Record

If there is at least one license activated with the same Host ID (on the same machine), edit the license activation record instead.

Activation and License Activation Management screen

[usage instructions](#).

Installations status filter:

Activated

☒ Enable license select during online activation

Profile ID	First Name	Last Name	Email	Date	Host Id	Installation status	Activated products	Get key	Personal comment
563775	John	Doe	john.doe@example.com	06/10/16	e06995357770	Activated	• MagicDraw 18.4 FR Teamwork Server, over 10 connections Click to edit	Send Download	Click to add

- 4. In the open dialog, provide the personal information of the user, who is going to use the modeling tool **(A)**, paste the copied Host ID **(B)**, and from the **Licenses to activate** list, select the purchased license of the Teamwork Server **(C)**.

Manage Your Licenses | No Magic - Google Chrome

registration.nomagic.com/manage/bind

CREATE NEW LICENSE ACTIVATION RECORD

Main information **Comment**

Personal information

First Name: John

Last Name: Doe

E-mail: john.doe@example.com

Phone: +1-214-291-9111

Role: Analyst

Industry: Aerospace

Company: example.com

Country: United States

Host ID

Host ID: e06995357770

Host ID is the value of a specific system attribute (MAC / Ethernet address) that uniquely identifies the host / machine under which an application is running. For the Host ID determining instructions of the particular product refer to the following link: <http://www.magicdraw.com/CommercialLicenseActivation#hostid>

Licenses to activate

MagicDraw 18.4 FR Teamwork Server, 5 connections

There are no purchased plugins or all purchased plugins are already activated.

Teamwork Server Client Version Limit

18.5

Save



IMPORTANT

If you are going to use Teamwork Server 17.0.4 or later, you can specify the client versions that are compatible with the server (Teamwork Server 17.0.4 or later can accept connections from newer versions of modeling tool). For this, select the appropriate client version number in the **Teamwork Server Client Version Limit** drop-down list. In the result, the selected version, and all the prior versions of clients, will be able to connect to the server. For more information about the client and Teamwork Server compatibility, see http://www.nomagic.com/support/compatibility.html#teamwork_server

5. Click **Send** or **Download** in the **Get key** column to receive the activated commercial license.