

Creating new generic table type

The **Customize Generic Table Wizard** contains the following steps for creating a new diagram type or modifying a chosen one:

- [Step 1: Specify diagram type and icon](#)
- [Step 2: Specify used projects](#)
- [Step 3: Specify Generic Table properties](#)

Step 1: Specify diagram type and icon

To create your own diagram, first specify the following properties:

- Diagram type name (for example, Generic Table).
- Abbreviation – a short form of the diagram name. It will be used in Diagram Frames header or Diagram shapes in Content diagrams.
- Category – creates your specific category in the **Diagrams** menu or in the **Create Diagram** command list. You can store all your customized diagrams in this category. If you keep this field empty, the customized diagrams will be added to the **Custom Diagrams** category.
- Help ID – sets a specific Help ID that invokes help or documentation topics.
- Icons – several icons for your custom diagram representation in MagicDraw GUI.

The screenshot shows the 'Customize Generic Table Wizard' dialog box. The title bar is blue with a close button. The main area has a light blue header with the text 'Specify basic diagram type information' and a sub-header 'In order to create or edit Generic Table type specify the following: its name, abbreviation (used for system purposes only), category to which the new diagram will belong, and customized diagram type icons'. On the right, there is an icon of a document with a hammer and a star. The main content area is divided into two parts. On the left, there are three radio buttons: '1. Specify diagram type and icon' (selected), '2. Specify used projects', and '3. Specify Generic Table properties'. On the right, there are four text input fields: 'Type:' (containing 'Generic Table'), 'Abbreviation:' (containing 'Generic'), 'Category:' (containing 'Table Diagrams'), and 'Help ID:' (containing 'Generic+Table'). Below these fields is an 'Icon' section with two columns: 'Lower DPI (16x16)' and 'High DPI (SVG)'. Each column has a preview of a table icon, a 'File' button, a 'URL' button, and a 'Remove' button. At the bottom of the 'Icon' section, there is a note: 'Lower DPI" bitmap icon is used for Model Browser and Menu. High DPI" icon is used for drawing, Create Diagram dialog, and High DPI monitors.' At the bottom of the dialog, there are five buttons: '< Back', 'Next >', 'Finish', 'Cancel', and 'Help'.

Customize Generic Table Wizard

Specify basic diagram type information

In order to create or edit Generic Table type specify the following: its name, abbreviation (used for system purposes only), category to which the new diagram will belong, and customized diagram type icons

☒ 1. Specify diagram type and icon

☐ 2. Specify used projects

☐ 3. Specify Generic Table properties

Type: Generic Table

Abbreviation: Generic

Category: Table Diagrams

Help ID: Generic+Table

Icon

Lower DPI (16x16) High DPI (SVG)

File URL Remove File URL Remove

Lower DPI" bitmap icon is used for Model Browser and Menu.
High DPI" icon is used for drawing, Create Diagram dialog, and High DPI monitors.

< Back Next > Finish Cancel Help

Step 2: Specify used projects

Custom Diagrams are oriented to a new specific domain, technology or platform, and are often based on a custom profile.

Select the required used projects or profile.

Customize Generic Table Wizard

Specify used projects
Add or remove projects that will be used by the custom diagram type. Use the Diagram Stereotype button to choose stereotypes from the used profile which will be applied to the diagrams of this type.

☐ 1. Specify diagram type and icon

☒ 2. Specify used projects

☐ 3. Specify Generic Table properties

Projects that will be used in the new diagram type:

UML_Standard_Profile.mdzip

Add

Remove

Diagram Stereotype

< Back

Next >

Finish

Cancel

Help

Do not remove the UML Standard Profile, which is selected by default, from the list. It must be used by any custom diagram type.

Click the **Diagram Stereotype** button to apply the specific stereotype to your Generic Table.

Step 3: Specify Generic Table properties

This step allows you to specify the appearance of a new Generic Table.

Property Name	Description
Show Column Icons	Set to true to show icons in column headers.
Custom Columns	Click ... to select and specify operations for calculating/gathering values of the custom column.
Display Mode	Click ... to select one of the visualization options: <i>Complete tree</i> (the table represents all elements with their owners), <i>Compact tree</i> (the table combines grouping elements), or <i>List</i> (selected model elements are organized into a plain list).
Show Scope As Root	Set to <i>true</i> to show scope as a root node in the tree display mode.
Show Element Number	Set to <i>true</i> to display the element number in the name column.
Row Element Type	Click ... to select the type of elements to be shown as row elements.
Query	Click ... to select and specify operations to query the model.

Types Include Subtypes	Set to <i>true</i> to include subtypes of the selected elements.
Columns	Click ... to select columns to appear in the Generic Table.
Row Filters	Set to <i>true</i> to display filtered rows in the Generic Table.
Show Detailed Column Name	Set to <i>true</i> to show classifiers next to properties in the column header.
Column Width	Click to adjust the width of columns.
Default Row Elements Owner	Click to select the default owner of row elements.
Hide Columns	Click ... to select columns that will not be displayed in the Generic Table.
Show Full Path	Set to <i>true</i> to show the full path of elements.
Show Filter	Set to <i>true</i> to show the filter applied in the Generic Table.
Show Element Type	Set to <i>true</i> to show the element type specification box in the criteria area of the Generic Table.
Show Scope	Set to <i>true</i> to display the scope in the criteria area of the Generic Table.
Legends	Click ... to select a legend for the Generic Table.
Description Area	Specify the description of the Generic Table.