Exporting documents to PDF and HTML

On this page

- Exporting tables
- Installing additional fonts

Cameo Collaborator for Teamwork Cloud allows you to export an open document or a part of it to PDF and HTML formats.

Customizing PDF templates and can be modified according to your needs. You can find them in the <Web_App_Platform_installation_directory>lap ache-tomcat\shared\conf\data\collaborator\pdf directory.

Export to PDF/HTML limitations default, you can export up to 400 sections to PDF and up to 3000 sections to HTML.

To change the export to PDF/HTML limits:

To export a Gemen & Weber at po denote the Ran and the

- 2. Do one or both of the following:
- Open the Cameo Collaborator document you want to export.
 Add the export.limit.size.pdf property to the file and specify the maximum number of sections to be exported to PDF as its value (the
 Click on right side of the app bar and in the open menu select Export document to PDF or HTML.
 In the open wizard, click the Document scope drop-down box and select one of the following scope options:
 - - Active rections resentation elements selecting this option allows you to choose which elements of the active section should be exploredetaultispallayeeid Belooy.
 - 3. Restart Web Application Platform

| C | Scope 2 Pro | perties |
|---|--|---------|
| | Document scope * Active section's presentation elements 💌 | |
| | House | · |
| | Characteristics Hyperlinks | |
| | Parts Detailed View | - |
| | CANCEL NEXT | |

- Active view exports the open view of the document which is selected in the app bar.
- · Whole document exports the whole document.
- 4. Click the Next button.
- 5. In the second step of the wizard, chose the format of the target document by selecting the PDF or HTML radio button.

| 🖉 Scope — | 2 Properties |
|-----------|-------------------|
| Format: | Options: |
| PDF | Cover page |
| O HTML | Table of contents |
| | CANCEL FINISH |

- 6. If needed, enable the following export options:
 - Turn on the Cover page switch to add a cover page to the target document. A cover page contains Cameo Collaborator document name, export date, project and document information.
 - Turn on the Table of contents switch to add a page with the table of contents to the end of the target document.
- 7. Click the Finish button.

After completing the above steps, the generated PDF or HTML document is downloaded to your computer. Note that exporting a large document may take a while, so be patient while the document is being generated.

Exporting tables

You can also generate PDF/HTM files directly from Generic, Instance, and custom tables. When you export a Cameo Collaborator document directly from a table, this table is automatically selected the export scope.

To export a table to PDF/HTML

- 1. In a Cameo Collaborator document, navigate to a table you want to export.
- 2. Click on the top right corner of the table and select **Export to PDF or HTML**.

| ≡ © | Structure 👻 | Q Search | | Climate Control System 🔲 🏭 🕒 : |
|-----|--------------------|-----------|----------------------------|--|
| Do | cumentation | | | ^ |
| Ор | en in Model Editor | | Climate Control System | |
| Ŧ | Value Prope | rties | | 🖾 Export to PDF or HTML _զ իդ |
| # | Name | Туре | Multiplicity Default Value | Documentation |
| 1 | WantedTemp | 🔽 Integer | (Unspecified) | |
| 2 | CabinTemp | 🔽 Integer | (Unspecified) | |
| 3 | OutsideTemp | 🔽 Integer | (Unspecified) | |
| 4 | CCStatus | | (Unspecified) | |
| 5 | Initialize | 🔽 Integer | (Unspecified) | |
| 6 | Counter | 🔽 Integer | (Unspecified) | |
| 7 | ManualMode | Integer | (Unspecified) | |

3. In the open wizard, chose the format of the target document by selecting the PDF or HTML radio button.

- 4. If needed, enable the following export options:
 Turn on the Cover page switch to add a cover page to the target document. A cover page contains Cameo Collaborator document name, export date, project and document information.
 Turn on the Table of contents switch to add a page with the table of contents to the end of the target document.

the scope of the target document is the table from which you have initiated the export command. To change the scope, click the Scope step on the top left corner of the wizard dialog.

| 5. C | lick the Finish button. | |] | | | | |
|---------------------------------------|--|--------------|-------------------------------------|--|--|--|--|
| Installi If your Car as describ | ne 🖉 Scope — | 2 Properties | stall Microsoft TrueType core fonts | | | | |
| To install a | ed Format: | Options: | | | | | |
| 1. Ir | nt 🧿 PDF | Cover page | | | | | |
| | <pre>sud mt.s.n.d.nae.ac.nsflance.t.naflg sud wget http://rpmfind.net/linux/epel/7/x86_64/Packages/c/cabextract-1.9-7.el7.x86_64.rpm sud rpm -Uvh cabextract-1.9-7.el7.x86_64.rpm sud wget ftp://ftp.pbone.net/mirror/olea.org/msttcore-fonts-2.0-6.noarch.rpm sud rpm -Uvh msttcore-fonts-2.0-6.noarch.rpm sud fc-cache -fv</pre> | | | | | | |

2. Restart Web Application Platform.