

Capability Provision Creation Wizard

The **Capability Provision Creation Wizard** is used to define a Capability Provision by one or more Actual Resources at a specific period of time.

To open the **Capability Provision Creation Wizard**

1. Open a [CV-3](#) (DoDAF), StV-3 (MODAF), NCV-3 (NAF), [Cr](#) (NAF 4.0), or Strategic Phasing diagram (UAF).
 2. Select a Capability.
 3. Do one of the following:
 - On the <viewpoint name> diagram toolbar, click **Add New > Capability Provision**.
 - On the diagram pane, right-click the Capability and select **Add New Capability Provision**.
- The **Capability Provision Creation Wizard** opens.


The wizard consists of three steps:

- 1 [Actual Resources selection](#)
- 2 [Capability service date specification](#)
- 3 [Out of service date specification \(Optional\)](#)

Actual Resources selection

In this step, you can select the existing or create new Actual Resources.

 more information on selecting elements, see [Diagram Creation Wizard](#), Step #2.




The screenshot shows the 'Capability Provision Creation Wizard' window, specifically the 'Select Resource' step. The window has a blue title bar with the text 'Capability Provision Creation Wizard' and a close button. Below the title bar, there's a section titled 'Select Resource' with a subtitle: 'Search for existing or create new Resource to provide capability represented by the active row in the chart in the specified time frame.' To the right of this section is a graphic showing three overlapping circles (yellow, green, blue) with arrows indicating a cycle, and a wrench icon. On the left side of the main panel, there are three radio buttons for step selection: '1. Select Resource' (selected), '2. Specify In Service date', and '3. Specify Out Of Service date'. The main panel features a search bar at the top with a magnifying glass icon. Below the search bar are two tabs: 'Tree' and 'List'. The 'List' tab is active, showing a list of resources. The list starts with '<UNSPECIFIED>' and includes items like 'Air Transit', 'Aircraft' (highlighted in blue), 'Aircraft Control Subsystem', 'Allocate Resources', 'Boat', 'C2 Organization', 'C2 System', 'CapabilityConfiguration1', 'Commander', and 'Communicate Status'. To the right of the list, it says 'Showing 30 matches' and a 'More' button. At the bottom of the list, there's a checkbox for 'Apply Filter (Ctrl+Space)' and a 'Creation Mode' button. At the very bottom of the window, there are five buttons: '< Back', 'Next >', 'Finish', 'Cancel', and 'Help'.


Capability service date specification

In this step, you can set the date and time, when the Actual Resource should begin provisioning the Capability. The In Service Milestone is created.


 more information on setting the day and time, see [Date and Time Settings](#) dialog.



Capability Provision Creation Wizard




Specify In Service date
Specify date for selected Resource configurations to start providing Capability represented by the active row.



☐ 1. Select Resource

☒ 2. Specify In Service date

☐ 3. Specify Out Of Service date

Select timeline:
 Timeline

Set the date and time:
2020-09-01

Change the date format:
YYYY-MM-DD

Date:

September 2020						
Sun	Mon	Tue	Wed	Thu	Fri	Sat
30	31	1	2	3	4	5
6	7	8	9	10	11	12
13	14	15	16	17	18	19
20	21	22	23	24	25	26
27	28	29	30	1	2	3
4	5	6	7	8	9	10

Date:
2020-09-01

Today

Time:
13:19:06

Now

Time zone:
+02:00

Default

< Back

Next >

Finish

Cancel

Help

Out of service date specification (Optional)

In this step, you can specify when the Actual Resource should stop provisioning the Capability. The Out Of Service Milestone is created. This step is optional. If you skip this step, the Capability exhibition bar on the chart will have the triangle ending.

 more information on setting date and time, see [Date and Time Settings](#) dialog.

Capability Provision Creation Wizard

Specify Out Of Service date

Specify date for selected Resource configurations providing Capability represented by the active row to go out of service.

☐ **1. Select Resource**
☐ **2. Specify In Service date**
☒ **3. Specify Out Of Service date**

Select timeline:

Timeline

Set the date and time:

2021-09-01

Change the date format:

YYYY-MM-DD

Date:

September 2021						
Sun	Mon	Tue	Wed	Thu	Fri	Sat
29	30	31	1	2	3	4
5	6	7	8	9	10	11
12	13	14	15	16	17	18
19	20	21	22	23	24	25
26	27	28	29	30	1	2
3	4	5	6	7	8	9

Date:

2021-09-01

Today

Time:

13:21:15

Now

Time zone:

+02:00

Default

< Back

Next >

Finish

Cancel

Help

Related diagrams

- [CV-3 Capability Phasing](#)
- [MODAF. StV-3 Capability Phasing](#)
- [NCV-3 Capability Phasing](#)
- [Cr Capability Roadmap](#)
- [Strategic Roadmap](#)