

Plugin licensing

On this page

- [Adding the license key file](#)
- [Activating at nomagic.com](#)
- [Obtaining the floating license](#)

On this page

[Link](#)

Adding the license key file

1. In the **Resource Plugin Manager** dialog, click the **Manage Licenses** button.
2. In the modeling tool **License Manager** dialog, click the **Select License Key Files** button. Then in the **Select Key File** dialog, select the license key file and click **Open**.
3. In the **License Configuration** dialog, check the license information and click **OK**.
4. When you receive the message to restart the modeling tool, click **OK**.
5. Restart the modeling tool.

Activating at [nomagic.com](#)



Before starting the plugin license activation, make sure plugins are [installed](#).

1. Log in at [nomagic.com](#) as license owner.
2. At the right side of the webpage, under **Members**, click **License Activation Management**.
3. In the **License Activation Management** page, click the **Click to Edit** button to edit the record of the modeling tool for which you want to activate plugins.

4. In the **Edit license activation record** dialog, select the plugins you want to activate.

Manage Your Licenses | No Magic - Google Chrome

registration.nomagic.com/manage/editbind/id/0022dddd2222_499111

EDIT LICENSE ACTIVATION RECORD

Add New Licenses **Deactivate**

Plugin licenses

With the activated application, you can activate the following plugins:

- SysML Plugin 18.4 FR Seat License
- UPDM 2 Plugin 18.4 FR Seat License
- Cameo Simulation Toolkit Plugin 18.4 FR Seat License
- Merge Plugin 18.4 FR Seat License
- Cameo Business Modeler Plugin 18.4 FR Seat License
- Cameo Data Modeler Plugin 18.4 FR Seat License
- Cameo SOA+ Plugin 18.4 FR Seat License
- ParaMagic Plugin 18.0 LTR Seat License
- ParaMagic Lite Plugin 18.0 LTR Seat License
- Cameo Requirements Modeler Plugin 18.4 FR Seat License
- Cameo DataHub Plugin 18.4 FR Seat License
- UPDM 3 Plugin 18.4 FR Seat License

Client licenses

Save



- If you want to activate the license for the **SysML Plugin bundle**, you must add both commercial plugins included in that bundle to the activation record: SysML Plugin and Cameo Requirements Modeler Plugin.
- If you want to activate license for **UPDM 2 Plugin bundle**, you must add all commercial plugins included in that bundle to the activation record: UPDM 2 Plugin, SysML Plugin, and Cameo Requirements Modeler Plugin.

1. Click **Save** when finished. The activation record is updated.
2. In the **Activation Records** table, in the **Get key** column, click the *Send* button to receive the license key by email or click the *Download* button to save the key locally.
3. Add the license key and restart the modeling tool.

Obtaining the floating license



- Make sure your floating license server contains the plugin license.
- Make sure the plugins are installed.

1. Start the modeling tool.
2. On the **Help** menu, click **License Manager**.
3. In the modeling tool **License Manager** dialog, click the **Use Floating License** button.
4. In the **FLEXnet License Server Connection** dialog, enter server name and port and click **OK**.




Your system administrator provides the server name and port.

5. In the **Select Edition/Plugin** dialog, select edition and plugins and click **OK**.



If the **Automatically login each time <modeling tool> is started** check box is selected, the **FLEXnet License Server Connection** dialog will not be displayed and the licenses will be obtained automatically. If you need to reset the licenses or select additional ones, do the following:

1. In the main menu, click Options > Environment. The **Environment Options** dialog opens.
2. In the **Floating** options group, set the **Auto login to FLEXnet License Server** option to *false*.
3. Restart the modeling tool.



[Link](#)