

# Diagram banners

## On this page


- [Creating diagram banners](#)
- [Editing diagram banners](#)
- [Removing diagram banners](#)

You can create diagram banners, such as a header and/or footer, to display important information on the diagram. The banners are not included in the diagram frame but are contained within the diagram pane; thus, if you choose to export the diagram ([save it as an image](#) or [print it](#)), the banners are included. The diagram banners can be created for all diagram types, e.g. tables, matrices, or maps.


## Creating diagram banners

To create a diagram banner

1. Right-click the diagram. In the shortcut menu, select **Stereotype**. The Stereotype selection menu opens.
2. In the Stereotype selection menu, select the «banner» stereotype check mark. Click the **Apply** button.




3. Right-click the diagram again and open its Specification window.
4. In the Specification window, click the **Tags** property group.
5. Under the «banner» stereotype, select the **text** tag and click the **Create Value** button.




6. In the **Value** box on the right side of the dialog, write the text that you want to have displayed on the diagram banner.
7. In the toolbar of the right-side compartment, next to the **Display** option, select the position for the diagram banner from the dropdown menu.

- a. **Header** - the diagram banner will be displayed at the top of the diagram. This is the default option.
- b. **Footer** - the diagram banner will be displayed at the bottom of the diagram.
- c. **Both** - the diagram banner will be displayed at the top and bottom of the diagram.
- d. **None** - the diagram banner will not be displayed on the diagram.



8. (Optional) To create additional banners for the diagram, click the **Add** button and follow the steps 6-7.
9. Click **Close**. The diagram banner is created.



## Editing diagram banners

To edit the diagram banner text and/or display position

1. Right-click the diagram and open its **Specification window**.
2. In the Specification window, click the **Tags** property group.
3. Select the **text** value under the «banner» stereotype.
4. In the **Value** box on the right-side compartment, select the **text** value you want to edit and click the **Edit** button.
5. Edit the text of the banner and/or the display position via the **Display** option for the selected **text** value.
6. Click **Close**.

## Removing diagram banners

To remove a diagram banner

1. Right-click the diagram and open its **Specification window**.
2. In the Specification window, click the **Tags** property group.
3. Select the **text** value under the «banner» stereotype.
4. Do one of the following:
  - a. To remove all banners, click the **Remove Value** button.
  - b. To remove a single banner, in the **Value** box on the right-side compartment, select the **text** value you want to remove and click the **Remove** button.
5. Click **Close**.