Obtaining a floating license for a modeling tool

On this page

- Prerequisites
- Procedure
- Finishing offline floating license session

Prerequisites

- The floating license server (FlexNet or DSLS) is installed and started.
- You have the floating license server name and port (provided by your system or license server administrator).

Procedure

- 1. Start the modeling tool.
- 2. When the License Manager dialog opens, click the Use Floating License button.

toopen this dialog manually, select **Help** > License Manager.

- 3. In the License Server Connection dialog, select one of the following:
 - a. FlexNet. Enter the floating license server name and port (provided by your system or license server administrator). Click OK.

🕱 License Ser	ver Connection		—		×
FlexNet	DSLS				
Server Name:	localhost				
Port:	1101				
Automatio	cally login each	time Magic Cyber Syst	ems Enginee	r is starte	d
ОК	Cancel	Switch to Standalor	ne/Mobile	Hel	p

b. DSLS. Select one of the options:

- i. Organization defined. Provides access via the licensing servers specified in a file on the client's computer licensing directory. Can be either set by the user or by the server administrators up front. Click **OK**.
- ii. Custom. Input the server address (must include the port number, which is 4085 by default. e.g., myaddress:4085). Click OK.

X License Server Connection	—		×		
FlexNet DSLS					
Organization defined					
⊖ Custom					
Servers:					
Automatically login each time Magic Cyber Systems Engineer is started					
OK Cancel Switch to Standalone	/Mobile	He	lp		
0					



4. In the Select Edition/Plugin dialog, sale of the modeling tool edition plugins you want to use, and the floating line is consection type: online or offline (borrowing). Click OK.

Select Edition	alog will not be disp /Plugin	blayed, and the lice	nses will be obtaine	l automatically. To re	eset the licenses o	r select additional ones,
Edition	o the following.					
Architect (1. In the main 0 of 250 hit for Froat	menu, click Option	is > Environment. set the Auto Loain	to the License Serve	o tions dialog oper er option to <i>false</i> .	IS.
 Enterprise 	3. Restart the (23 of 50 licenses	modeling tool. are in use)				
O Profession	🗶 License Serv	er Connection		-	o x	
O Profession	FlexNet	DSLS				T
O Profession	Server Name:	localhost				
◯ Standard	Port:	1101				
- Plugins	Automatic	ally login each t	ime Magic Cybe	r Systems Enginee	r is started	
Cameo Re	ОК	Cancel	Switch to Star	dalone/Mobile	Help	
Project Mer	ge (55 of 100 lice	enses are in use)				
(20	-£ 100 k					
∑ Sysmic (20	of 100 licenses ar	e in use)				
Remember plug	in selection for th	e next time				
	Refresh Use	d Licenses				
Connection						
Online						
Offline						
Borrow period in	hours (1 - 1 440)	: 24 🔹				
	ОК	Cancel	Help			
Offline licens Offline licens FlexNet lice	e support le (borrowed) licens ense borrowing is n	ses are not support	ed on macOS/Linux acOS machines run	. See the DSLS insta ning with ARM Java.	llation and licensir See the FlexNet li	ng page. cense server installation
Bobtain a floating	license for your plu	gin, you must insta	ll it in your modeling	tool first. Once the p	lugin is installed, y	vou will find it listed under P
Check the license	e information, selec	t Help > About and	d click the Licensin	a piugin. g tab.		

Finishing offline floating license session

To finish an offline floating license session earlier

1. In the main menu, click Help > Finish Offline License Session.



2. Click Yes.