

Generating an HTML table from a UI table, Time series chart, and CSV export configuration

On this page


- [Generating an HTML table from a UI table](#)
- [Generating an HTML table from a Time series chart and CSV export configuration](#)

Generating an HTML table from a UI table


This feature of Cameo Simulation Toolkit enables you to export MagicDraw HTML tables in UI modeling diagrams to HTML5, allowing them to be viewed in a web browser. The sample model used on this page, [SpacecraftMassRollup](#), demonstrates how to create a User Interface table in the User Interface Modeling diagram, generate HTML, run the simulation, and view the UI table in HTML5 in your web browser. You can download [SpacecraftMassRollup](#) at the end of this page.

To generate an HTML table from a UI table component


1. Open [SpacecraftMassRollup](#) from the MagicDraw installation file: *folder\samples\simulation*.
2. Right-click the Model element in the Containment tree. Select **Create Diagram > Other Diagrams > User Interface Modeling Diagram**.



3. Drag a UI table component onto the newly created diagram.



4. Drag the **spacecraft** Block from the **Structure** Package in the Containment tree to the table.



5. Select **Create UI Prototype**. The table headers will change from **Column 1** and **Column 2** to **Name** and **Value**.

 **Tip:** If you drag the **spacecraft** Block to the table quickly, the column name will change automatically, without having to select **Create UI Prototype**.


Column 2	Column 1
	Create UI Prototype
	Create Block spacecraft Symbol

Selecting the **Create UI Prototype** menu that appears after dragging the **spacecraft** Block to the table.


Name	Value

When you select the **Create UI Prototype**, the table column names change to Name and Value.


6. Right-click the UI table. Select **Specification** to bring up its Specification window as shown below. Note that the Classifier is assigned to the **Represents** property.




7. Click beside the **Value** property and select the values you want to monitor from the tree view in the **Select Nested Properties** dialog.
8. Click . The selected values will appear in the **Value** property in the UI table Specification window.




9. Close the Specification window.
10. Click the Generate HTML button on the MagicDraw toolbar.



11. Run the *spacecraft mass analysis* Simulation Configuration. The Console messages will appear.




Running the *spacecraft mass analysis* Simulation Configuration.



The Console messages appearing in the Simulation Console with the filter Options set to Warn.

12. Note that a simulation web server has started. You can open the Specification window of Simulation Configuration to see the **Start Web Server** (true) option.



13. Click the HTTP link, e.g., <http://10.1.1.60:8080/> in the **Console** pane to view the simulation in real-time in your browser.


Note
The preferred browser is **Google Chrome**.

Name	Value		
propulsion.tank.me	38.0	✖	↑↓
propulsion.thruster.me	30.0	✖	↑↓
propulsion.me	68.0	✖	↑↓
me	95.0	✖	↑↓
telecom.amplifier.me	8.0	✖	↑↓
telecom.antenna.me	19.0	✖	↑↓
telecom.me	27.0	✖	↑↓

Export Data

14. You can edit the values from the web browser page; the simulation engine will automatically pick the values up and re-calculate.

If you edit the **Documentation/Hyperlink** tag from the UI table's specification window and run the simulation again, they will show up as the table's descriptions. See the following two figures



Changing the Documentation/Hyperlinks tag will reflect on the table's descriptions in the browser.

The screenshot shows a web browser window titled "spacecraft" at the URL "10.1.1.60:8080". The page displays a table with the title "My Table Description". The table has two columns: "Name" and "Value". Each row contains a name, its current value, and two status indicators: a red "X" and a blue "up-down" arrow. A green "+" button is located at the top right of the table. A blue "Export Data" button is at the bottom left.

Name	Value		
propulsion.tank.me	38.0	✗	↑↓
propulsion.thruster.me	30.0	✗	↑↓
propulsion.me	68.0	✗	↑↓
me	95.0	✗	↑↓
telecom.amplifier.me	8.0	✗	↑↓
telecom.antenna.me	19.0	✗	↑↓
telecom.me	27.0	✗	↑↓

The changes to the Documentation/Hyperlinks tag appearing as the HTML table's description.


HTML tables are supported for Time series charts and CSV Export configurations.

Generating an HTML table from a Time series chart and CSV export configuration

An HTML table can also be generated from a Time series chart and CSV export configuration.

To generate an HTML table from either a Time series chart or a CSV export configuration

-
1. Right-click a Time Series Chart or a CSV Export configuration and choose **Tools > Generate HTML Table**.



2. This will generate an HTML file, which can be viewed either online or offline. A message stating, "INFO: HTML table(s) is/are generated to the C:\Users\Downloads\CoffeeMachine_test1 folder," in the Console pane will appear in the **Simulation Console** pane.

Sample model

The model used in the figures on this page is the **SpacecraftMassRollup** sample model that comes with your modeling tool.

To open this sample, do either of the following

- Download [SpacecraftMassRollup.mdzip](#).
- Find it in the modeling tool <modeling tool installation directory>\samples\simulation\SpacecraftMassRollup.mdzip.