

# Working with Strategic Phasing diagram

## On this page

- [Creating Strategic Phasing diagram](#)
- [Adding Capabilities](#)
- [Adding Sub Capabilities](#)
- [Adding Capability Provisions](#)
- [Displaying all Sub Capabilities](#)
- [Displaying Sub Capabilities deleted from diagram](#)
- [Deleting Capabilities](#)
- [Deleting Sub Capabilities](#)
- [Removing Capability Provision](#)

## Creating Strategic Phasing diagram

When you choose to create Strategic Phasing diagram, [Strategic Phasing Creation Wizard](#) opens.

To create a Strategic Phasing diagram from the wizard

1. Right-click the Strategic Roadmap Package and select **Create Diagram > Strategic Phasing**.
2. Follow the steps of the [Strategic Phasing Creation Wizard](#).
3. Click **Finish** when you are done.



If you do not wish to use the [Strategic Phasing Creation Wizard](#) next time, clear the **Show the wizard next time, when I create Strategic Phasing** check box.

To create an Strategic Phasing diagram manually when [Strategic Phasing Creation Wizard](#) is disabled

1. Right-click the Strategic Roadmap Package and select **Create Diagram > Strategic Phasing**.
2. Type the diagram name.
3. Press Enter.  
The blank Strategic Phasing chart is created.



To restore the usage of the [Strategic Phasing Creation Wizard](#)

## Adding Capabilities

Capabilities Environment.

To add a new Capability

2. In the **Environment Options** dialog select the **UAF** options group.
3. In the General properties, set the **Show CV-3/StV-3/NCV-3 Creation Wizard each Time Creating New Chart** property value to *true*.
1. On the Strategic Phasing diagram toolbar, click **Add New > Capability**.  
An empty line for the newly created Capability appears on the diagram pane.

To add an existing Capability

1. On the Strategic Phasing diagram toolbar, click **Add Existing > Capability**.
2. In the **Select Capability** dialog, select a Capability and click the **+** button.
3. Click **OK** when you are done

## Adding Sub Capabilities

To add a new Sub Capability

1. Select the Capability for which you want to create a Sub Capability.
2. Do one of the following:
  - On the Strategic Phasing diagram toolbar, click **Add New > Sub Capability**.
  - From the shortcut menu of the selected Capability, select **Add New Sub Capability**.
3. An empty line for the newly created Capability appears.

To add an existing Sub Capability

- 
1. Select the Capability for which you want to add a Sub Capability.
  2. Do one of the following:
    - On the Strategic Phasing diagram toolbar, click **Add Existing > Sub Capability**.
    - From the shortcut menu of the selected Capability, select **Add Existing Sub Capability**.
  3. From the **Select Capability** dialog, select a Capability and click the **+** button.
  4. Click **OK** when you are done.

## Adding Capability Provisions

To add a new Capability Provision

- 
1. Select the Capability for which you want to create a Capability Provision.
  2. Do one of the following:
    - On the Strategic Phasing diagram toolbar, click **Add New > Capability Provision**.
    - On the diagram pane, right-click the Capability and select **Add New Capability Provision**.
  3. Follow the steps of the **Capability Provision Creation Wizard**.
  4. Click **Finish** when you are done.

## Displaying all Sub Capabilities

To display all Sub Capabilities

- 
1. Select the Capability which Sub Capabilities you want to display.
  2. In the Strategic Phasing diagram toolbar, click the **Display All** button.

## Displaying Sub Capabilities deleted from diagram



The capability name becomes *Italic* when one or more sub capabilities are deleted from the chart.

To display deleted Sub Capability

- 
1. Select the Capability which Sub Capabilities you want to restore.
  2. From the selected Capability's shortcut menu, select **Display Deleted From Chart** and do one of the following:
    - Select the Sub Capability you want to be displayed.
    - Select **Display All** to display all deleted Sub Capabilities.

## Deleting Capabilities

To delete a Capability from the chart

- 
1. Select a Capability.
  2. On the diagram toolbar, click the **Delete From Chart** button.

To delete a Capability from the model

- 
1. Select a Capability.
  2. On the diagram toolbar, click the **Delete** button.

## Deleting Sub Capabilities

To delete a Sub Capability from the chart

- 
1. Select a Sub Capability.
  2. On the diagram toolbar, click the **Delete From Chart** button.

To delete a Sub Capability from the model

---

1. Select a Sub Capability.
2. On the diagram toolbar, click the **Delete** button.

## Removing Capability Provision

To remove Capability Provision

---

1. Right-click the Capability Provision.
2. Select **Remove Capability Provision**.
3. Choose the Capability Provision which you want to remove from the chart.