Project Status Application Wizard

The **Project Status Application Wizard** is used to apply the DLOD Milestone, DOTMLPF Milestone, or custom Milestone type to the selected element, which can be one of the following milestone kinds:

- In Service
- Deployed
- No Longer Used
- Out Of Service
- Other

To open the Project Status Application Wizard

1. On the diagram pane, right-click the Milestone and select Edit Status. The Project Status Application Wizard opens.

The wizard consists of two steps:

- 1 Actual Project Milestone Type selection
- 2 Project Status at a particular Milestone specification

Actual Project Milestone Type selection

In this step, select DLOD Milestone, DOTMLPF Milestone, or create your own Milestone type.

Project Status Application Wizard				
Select the existing or create a new Actual Project Milestone type. Selected milestone type defines project threads and status indicators for each of the project treads for specifying project status at a particular milestone.				
 I. Select Actual Project Milestone Type 2. Specify Project Status at a particular Milestone 	Q- List DLOD Milestone ✓ DOTMLPF Milestone	Selected elements: <i>I</i>		
< Back Next > Finish Cancel				

Project Status at a particular Milestone specification

In this step, specify project threads and status indicators of the selected Actual Project Milestone Type.

🔯 Project Status Application Wizard

Specify Project Status at a particular milestone To define Project Status at the particular Actual Project Milestone, select or create a new project thread and define its status indicator. Each project thread is defined by a different sector and each status indicator is defined by a different color in the project status circle. Project Thread Preview 1. Select Actual Project Milestone Type 📄 Add 🖷 Clone 🍵 Delete Equipment 2. Specify Project Status ۲ Logistics at a particular Milestone Personnel Information -Infrastructure Organization Doctrine/Concepts Doctrine/Concepts Training Information Personnel Training Status Indicators Organization 📄 Add 🍵 Delete 🍌 Fill Color quipment DLOD Absent Not Required Infrastructure J Logistics No Outstanding Issues Manageable Issues Critical Issues 窗 < Back Next > Finish Cancel

	Project threads	Status indicators
DLOD Milestone type	 Equipment Logistics Infrastructure Organization Doctrine/Concepts Information Personnel Training 	 DLOD Absent Not Required No Outstanding Issues Manageable Issues Critical Issues

x

Project Status Application Wizard

Specify Project Status at a particular milestone To define Project Status at the particular Actual Project Milestone, select or create a new project thread and define its status indicator. Each project thread is defined by a different sector and each status indicator is defined by a different color in the project status circle. Project Thread Preview 1. Select Actual Project Add 🖷 Clone 🍵 Delete Milestone Type Doctrine 2. Specify Project Status Organization at a particular Milestone Personnel Training Leadership Materiel Leadership Facilities Personnel Facilities Materiel Status Indicators Doctrine 📄 Add 🍵 Delete 🧄 Fill Color Training¹ Materiel Solution Analysis Technology Development Corganization Engineering and Manufacturing Dev Production & Deployment Operations & Support 窗 < Back Next > Finish Cancel

х

	Project threads	Status indicators
DOTMLPF Milestone type	 Doctrine Organization Training Materiel Leadership Personnel Facilities 	 Materiel Solution Analysis Technology Development Engineering and Manufacturing Development Production & Deployment Operations & Support

If you selected your own milestone type, you can create your own projects threads and status indicators.

To create project threads and status indicators

- 1. In the Project Thread area, click the Add button.
- 2. Specify the thread name.
- 3. In the Status Indicator area, click the Add button. 4. Specify the indicator name.
- 5. Click the Fill Color button.
- 6. In the Color dialog choose the color and click OK.

Ocreate a second thread with the same status indicators, select a previously created thread and click the Clone button. A new thread with previously

defined status indicators is created.

To remove the applied Project Status

- 1
 - In the right bottom corner of the Preview area, click

Related procedures

- Edit Project Status in Lr diagram
 Managing PV-2 diagram
 Removing Project Status from Lr diagram