

Working with StV-5 table

On this page

- [Creating StV-5 table](#)
- [Modifying StV-5 table](#)

Creating StV-5 table

The content of the StV-5 table are Resources used by Actual Organizational Resources (Actual Organizations and Actual Posts) to realize Capabilities in a particular time period. Rows of the StV-5 table are Actual Organizational Resources, and columns are Capabilities.

A relationship between an Actual Organizational Resource and a Resource is expressed by the Actual Project Milestone. There can be one or more Resources related to the Actual Organizational Resource.

A StV-5 table can be owned by an Enterprise Phase that will be the context element for this table. The Enterprise Phases are modeled in the StV-1 view.

A relationship between a Capability and a context element is represented by the Exhibits.

To add rows to a StV-5 table

1. Click the **Add Rows** button in the table toolbar or press Ctrl+Insert. The element **Selection** dialog will open.
2. Select Actual Organizational Resources you need to add to the table. For the detailed information about the element **Selection** dialog see [Selecting elements](#).
3. Click OK when you are finished.

To add resources to a StV-5 table

1. Click the cell wherein you want to add a resource.
2. Click the + button that will appear at the right of the selected cell. The [Deployment Milestones wizard](#) will open.
3. Using the [Deployment Milestones wizard](#) select resources and specify both deployment and no longer used dates for them.
4. Click **Finish** when you are done.

Modifying StV-5 table

Please refer to [Managing tables](#), if you are looking for the following table handling features:

- Delete the selected row.
- Delete the selected row from the table.
- Move the selected row up.
- Move the selected row down.
- Export a table to a plain text file format (.csv) or a Hypertext Markup Language format (.html).
- Generate a report.

To add/ remove columns to a StV-5 table

1. In the table toolbar, click the **Add/ Remove Columns** button. The element **Selection** dialog will open.
2. Select capabilities to add or remove from a table. For the detailed information about the element **Selection** dialog see [Selecting elements](#).
3. Click **OK** when you are finished.



- Capabilities will be removed only from the table. They will not be removed from the model.
- An Exhibits relationship between the context element and a removed Capability will be removed from the model.

To add/ remove resources to a StV-5 table

→ An Exhibits relationship between the context element and an added Capability will be added in the model.

1. Click the cell you want to edit.
2. The + and - buttons will appear at the right of the cell.
3. Do one of the following:
 - Click the + button to add a resource. The [Deployment Milestones wizard](#) will open.
 - Select a resource you want to remove and click the - button.



The Resource will be removed from the table, but not from the model.

