

Changing a TWCloud license

On this page:

- [Getting a new TWCloud license from the current license server](#)
- [Getting a new TWCloud license from another license server](#)

Changing a license or updating it through the **Server license** section on the **Settings** application requires a user with a **Server Administrator** role. Changing a license means returning the current one you are using to the FLEXnet License Server, setting the server capacity back to zero, and then leasing a new one.

License information
Here you can manage current server license.
Click 'Update license' to update the license TWCloud is running with.

License server
peleda:1101

Product	Version	Connection limit	Server	Database	Expiration
Enterprise	19.0	Unlimited	Single / Cluster	Single / Cluster	Permanent

UPDATE LICENSE

The Server license page.

The **License Information** section contains the details about the license server and the license key that is currently in use. Click the **Update License** button only if you want to change your license because it will cause the current license to be deleted and allow you to select one of the available licenses and use it.

Getting a new TWCloud license from the current license server

To get a new TWCloud license from the current license server

1. [Log into the TWCloud Admin](#) with an Administrator account.
2. Using App bar, navigate to **Settings** application.
3. Click the **Update License** button. A dialog informing that you are about to delete the license you are currently using will open.

Old license will be deleted
In order to update license old license will be deleted

CANCELUPDATE

4. Click **Update**.

 You cannot undo your action after clicking **Update**.

License information

Here you can manage current server license.

License server *

192.168.1.2:1101

Enter license server address and select the license for TWCloud (e.g. 192.168.1.2:1101)

SHOW LICENSES

5. Your current license server's address appears in the **License Server** box. Click the **Show Licenses** button. TWCloud Admin will update the license information and show all available license keys on the current license server in tabular form.

License information

Here you can manage current server license.

License server *

peleda:1101

	Product	Version	Connection limit	Server	Database	In use (available)	Expiration
☒	Business Pro	19.0	Unlimited	Single	Single / Cluster	11 (50)	Permanent
☐	Enterprise	19.0	Unlimited	Single / Cluster	Single / Cluster	13 (50)	Permanent
☐	Standard	19.0	10	Single	Single	0 (100)	Permanent
☐	Business	19.0	25+	Single	Single	3 (50)	Permanent

CANCEL CONFIRM

6. Select a new license key from the table and click the **Use license** button. Your new license will be applied and appear in the **Server License** section.

Getting a new TWCloud license from another license server

To get a new TWCloud license from another license server

1. [Log into the TWCloud Admin](#) with an Administrator account.
2. Using App bar, navigate to **Settings** application.
3. Click the **Update License** button. A dialog informing that you are about to delete the license you are currently using will open.
4. Click the **Yes** button.
5. Type the address and port of another license server in the **Server license** box.
6. Click the **Show License** button. All available license keys on the new server license will appear in tabular form.
7. Select a new license key from the table and click **Use license**. Your new license will be applied and appear in the **License Information** section.

Related pages

- [Sign into TWCloud Admin](#)