

# Working with Strategic Phasing diagram

## On this page

- [Creating Strategic Phasing diagram](#)
- [Adding Capabilities](#)
- [Adding Sub Capabilities](#)
- [Adding Capability Provisions](#)
- [Displaying all Sub Capabilities](#)
- [Displaying Sub Capabilities deleted from diagram](#)
- [Deleting Capabilities](#)
- [Deleting Sub Capabilities](#)
- [Editing Capability Provision](#)
- [Removing Capability Provision](#)


## Creating Strategic Phasing diagram

When you choose to create Strategic Phasing diagram, [Strategic Phasing Creation Wizard](#) opens.

 Increase the diagram readability, use legends. To learn how to use legends, see [Legends](#) chapter.

To create a Strategic Phasing diagram from the wizard

1. Right-click the Strategic Roadmap Package and select **Create Diagram > Strategic Phasing**.
2. Follow the steps of the [Strategic Phasing Creation Wizard](#).
3. Click **Finish** when you are done.

 If you do not wish to use the [Strategic Phasing Creation Wizard](#) next time, clear the **Show the wizard next time, when I create Strategic Phasing** check box.

To create an Strategic Phasing diagram manually when [Strategic Phasing Creation Wizard](#) is disabled

1. Right-click the Strategic Roadmap Package and select **Create Diagram > Strategic Phasing**.
2. Type the diagram name.
3. Press Enter.  
The blank Strategic Phasing chart is created.

 Restore the usage of the [Strategic Phasing Creation Wizard](#)

## Adding Capabilities Environment.

To add a new Capability

2. In the **Environment Options** dialog select the **UAF** options group.

3. In the General properties, set the **Show CV-3/StV-3/NCV-3 Creation Wizard each Time Creating New Chart** property value to *true*.

1. On the Strategic Phasing diagram toolbar, click **Add New > Capability**.  
An empty line for the newly created Capability appears on the diagram pane.

To add an existing Capability

1. On the Strategic Phasing diagram toolbar, click **Add Existing > Capability**.
2. In the **Select Capability** dialog, select a Capability and click the **+** button.
3. Click **OK** when you are done

## Adding Sub Capabilities

To add a new Sub Capability

1. Select the Capability for which you want to create a Sub Capability.
2. Do one of the following:
  - On the Strategic Phasing diagram toolbar, click **Add New > Sub Capability**.
  - From the shortcut menu of the selected Capability, select **Add New Sub Capability**.
3. An empty line for the newly created Capability appears.

To add an existing Sub Capability

---

1. Select the Capability for which you want to add a Sub Capability.
2. Do one of the following:
  - On the Strategic Phasing diagram toolbar, click **Add Existing > Sub Capability**.
  - From the shortcut menu of the selected Capability, select **Add Existing Sub Capability**.
3. From the **Select Capability** dialog, select a Capability and click the **+** button.
4. Click **OK** when you are done.

## Adding Capability Provisions

To add a new Capability Provision

---

1. Select the Capability for which you want to create a Capability Provision.
2. Do one of the following:
  - On the Strategic Phasing diagram toolbar, click **Add New > Capability Provision**.
  - On the diagram pane, right-click the Capability and select **Add New Capability Provision**.
3. Follow the steps of the [Capability Provision Creation Wizard](#).
4. Click **Finish** when you are done.

## Displaying all Sub Capabilities

To display all Sub Capabilities

---

1. Select the Capability which Sub Capabilities you want to display.
2. In the Strategic Phasing diagram toolbar, click the **Display All** button.

## Displaying Sub Capabilities deleted from diagram



The capability name becomes **highlighted** when one or more sub capabilities are removed from the chart.

To display deleted Sub Capability

---

1. Select the Capability which Sub Capabilities you want to restore.
2. From the selected Capability's shortcut menu, select **Show/Hide Sub Capabilities** and do one of the following:
  - Select the Sub Capabilities you want to be displayed.
  - Click **Select All** to display all removed Sub Capabilities.
3. Click **Apply**.

## Deleting Capabilities

To remove a Capability from the chart

---

1. Select a Capability.
2. On the diagram toolbar, click the **Remove From Chart** button.

To delete a Capability from the model

---

1. Select a Capability.
2. On the diagram toolbar, click the **Delete** button.

## Deleting Sub Capabilities

To remove a Sub Capability from the chart

---

1. Select a Sub Capability.
2. On the diagram toolbar, click the **Remove From Chart** button.

To delete a Sub Capability from the model

---

1. Select a Sub Capability.
2. On the diagram toolbar, click the **Delete** button.

## Editing Capability Provision

To edit Capability Provision

---

1. Right-click the Capability.
2. Select **Edit Capability Provision**.
3. Choose the Capability Provision which you want to edit. The [Capability Provision Creation Wizard](#) opens.
4. Edit the dates.
5. Click **Finish**.

## Removing Capability Provision

To remove Capability Provision

---

1. Right-click the Capability.
2. Select **Remove Capability Provision**.
3. Click the Capability Provision which you want to remove from the chart.

### Related procedures

- [Customizing Gantt chart properties](#)
- [Legends](#)