

Changing a license

Changing a license or updating it through the **Server license** section on the **Settings** application requires a user with a **Server Administrator** role. Changing a license means returning the current one you are using to the FLEXnet License Server, setting the server capacity back to zero, and then leasing a new one.

License information
Here you can manage current server license.
Click 'Update license' to update the license TWCloud is running with.

License server
peleda:1101

Product	Version	Connection limit	Server	Database	Expiration
Enterprise	19.0	Unlimited	Single / Cluster	Single / Cluster	Permanent

UPDATE LICENSE

The **License Information** section contains the details about the license server and the license key that is currently in use. Click **Update License** button only if you want to change your license because it will cause the current license to be deleted and allow you to select one of the available licenses and use it.

To get a new TWCloud license from the current license server

1. [Log into the TWCloud Admin](#) with an Administrator account or user with a **Server Administrator** role.
2. Using App bar, navigate to **Settings** application.
3. Click **Update License** button. A dialog informing that you are about to delete the license you are currently using will open.
4. Click **Update**.



You cannot undo your action after clicking **Update**.

License information
Here you can manage current server license.

License server *
peleda:1101

Enter license server address and select the license for TWCloud (e.g. 192.168.1.2:1101)

SHOW LICENSES

5. Your current license server address appears in the **License Server** box. Click **Show Licenses** button. TWCloud Admin will update the license information and show all available license keys on the current license server in tabular form.

License information
 Here you can manage current server license.

License server *
 peleda:1101

	Product	Version	Connection limit	Server	Database	In use (available)	Expiration
<input checked="" type="radio"/>	Business Pro	19.0	Unlimited	Single	Single / Cluster	11 (50)	Permanent
<input type="radio"/>	Enterprise	19.0	Unlimited	Single / Cluster	Single / Cluster	13 (50)	Permanent
<input type="radio"/>	Standard	19.0	10	Single	Single	0 (100)	Permanent
<input type="radio"/>	Business	19.0	25+	Single	Single	3 (50)	Permanent

CANCEL CONFIRM

- Select a new license key from the table and click **Use license** button. Your new license will be applied and appear on the **Server License** section.

To get a new TWCloud license from another Server license

- [Log into the TWCloud Admin](#) with an Administrator account.
- Using App bar, navigate to **Settings** application.
- Click **Update License** button. A dialog informing that you are about to delete the license you are currently using will open.
- Click **Yes** button.
- Type the address and port of another license server in the **Server license** box.
- Click **Show License** button. All available license keys on the new server license will appear in tabular form.
- Select a new license key from the table and click **Use license**. Your new license will be applied and appear on the **License Information** section.

Relate pages

- [Accessing TWCloud Admin](#)