

Configuration files

On this page

- [Getting the path to configuration files](#)
- [Storing configuration files in the installation directory or Common Application Data location on Windows](#)
- [Storing configuration files in a custom location](#)

A configuration file is where the initial parameters and settings of a program are defined. All default parameter values come with a program installation but you can edit configuration files and define your own values, for example, define the Java home directory. This page describes the locations where you can find the configuration files of your modeling tool, and how you can modify them and change their default storage location. Configuration files can be used to:

- Define application arguments
- Set the Java Home
- Change Java parameters (such as memory allocation)
- Update default Java classpath (advanced: for plugin developers)


The configuration files can be opened and modified using any standard text or code editor. Once modified, changing the default location of configuration files can allow you to store multiple configuration files for different versions of the tool.

This page covers all modeling tools:

- MagicDraw
- Cameo Enterprise Architecture
- Cameo Systems Modeler
- Magic Software Architect
- Magic Cyber Systems Engineer
- Magic Systems of Systems Architect

By default the configuration and auxiliary files of a modeling tool are stored in the following location:

OS	Configuration files storage
Windows Vista/7/8/10	C:\Users\<USERNAME>\AppData\Local\.<modeling tool name>\<modeling tool version number>
Other OS	<user.home>/.<modeling tool name>/< modeling tool version number>


**Modeling tool file naming**
In a file system, modeling tools' folders are named as follows:

Modeling tool	File name
Getting the path to configuration files MagicDraw	<i>magicdraw</i>
If you do not know the exact path to your modeling tool configuration files, follow the steps below to get it. Cameo Enterprise Architecture	<i>cameoea</i>
To get the path to your modeling tool configuration files Cameo Systems Modeler	<i>cameo.systems.modeler</i>
Magic Software Architect	<i>magic software architect</i>
1. From the Help menu, select About <modeling tool name> . The About dialog opens. 2. Click the Environment tab. 3. Click the hyperlink next to Configuration Files . The folder containing modeling tool configuration files opens.	<i>magic.cyber.systems.engineer</i>
Magic Cyber Systems Engineer	
Magic Systems of Systems Architect	<i>magic.systems.of.systems.architect</i>

You can also save configuration files in any of the following locations:

- <modeling tool installation directory>
- Common Application Data location (on Windows OS)
- Another directory


Storing configuration files in the installation directory or Common Application Data location on Windows

**Note**
The Common Application Data location on Windows Vista/7/8/10 is C:\ProgramData.

To store configuration files in the modeling tool installation directory or Common Application Data location on Windows


1. Open the *<modeling tool name>.properties* file, which is located in *<modeling tool installation directory>\bin*.
2. In the JAVA_ARGS line, change the **-DLOCALCONFIG** property value according to the following table:

-DLOCALCONFIG	=true	=false
Windows OSx	Common Application Data	Modeling tool installation directory
Other	<user.home>/.<modeling tool name>/< modeling tool version number>	Modeling tool installation directory

 **Important!**
It is important to add the **-DWINCONFIG=false** parameter on Window OS, otherwise, the configuration files will not be stored in the modeling tool installation directory.

You may also store configuration files in your custom location.

Storing configuration files in a custom location


 **Note**
If you have defined to store files in the modeling tool installation directory, files will not be stored in the defined location.

To store modeling tool configuration files in a custom location

Do either:

1. Open the *<modeling tool name>.properties* file, which is located in *<modeling tool installation directory>\bin*.
2. In the JAVA_ARGS line, add the following property:

```
-Dlocalconfig.location=<absolute path to a custom location>
```

 **Sample property value**
-Dlocalconfig.location=E:\temp\innerPack

Or:

1. Go to the folder, where [the configuration files are stored](#).
2. Create a new file named *magicdrawredirect*.
3. In the file, type the absolute path to the folder, wherein modeling configuration files will be saved, e.g., C:/<directory name>.

Related pages

- [Customizing environment options](#)
- [Customizing and Selecting Perspective](#)