

# Managing Cr diagram

You can manage the data in CV-3 diagram in the following ways:

- [Adding Capabilities](#)
- [Adding Sub Capabilities](#)
- [Adding Capability Provisions](#)
- [Displaying all Sub Capabilities](#)
- [Displaying Sub Capabilities deleted from diagram](#)
- [Removing Capabilities](#)
- [Removing Sub Capabilities](#)
- [Editing Capability Provision](#)
- [Removing Capability Provision](#)

## Adding Capabilities

To add a new Capability

---

1. On the Cr diagram toolbar, click **Add New > Capability**.  
An empty line for the newly created Capability appears on the diagram pane.

To add an existing Capability

---

1. On the Cr diagram toolbar, click **Add Existing > Capability**.
2. In the **Select Capability** dialog, select a Capability and click the **+** button.
3. Click **OK** when you are done

## Adding Sub Capabilities

To add a new Sub Capability

---

1. Select the Capability for which you want to create a Sub Capability.
2. Do one of the following:
  - On the Cr diagram toolbar, click **Add New > Sub Capability**.
  - From the shortcut menu of the selected Capability, select **Add New Sub Capability**.
3. An empty line for the newly created Capability appears.

To add an existing Sub Capability

---

1. Select the Capability for which you want to add a Sub Capability.
2. Do one of the following:
  - On the Cr diagram toolbar, click **Add Existing > Sub Capability**.
  - From the shortcut menu of the selected Capability, select **Add Existing Sub Capability**.
3. From the **Select Capability** dialog, select a Capability and click the **+** button.
4. Click **OK** when you are done.

## Adding Capability Provisions

To add a new Capability Provision

---

1. Select the Capability for which you want to create a Capability Provision.
2. Do one of the following:
  - On the Cr diagram toolbar, click **Add New > Capability Provision**.
  - On the diagram pane, right-click the Capability and select **Add New Capability Provision**.
3. Follow the steps of the [Capability Provision Creation Wizard](#).
4. Click **Finish** when you are done.

## Displaying all Sub Capabilities

To display all Sub Capabilities

---

1. Select the Capability which Sub Capabilities you want to display.
2. In the Cr diagram toolbar, click the **Display All** button.

## Displaying Sub Capabilities deleted from diagram



The capability name becomes **highlighted** when one or more sub capabilities are removed from the chart.

To display deleted Sub Capability

1. Select the Capability which Sub Capabilities you want to restore.
2. From the selected Capability's shortcut menu, select **Show/Hide Sub Capabilities** and do one of the following:
  - Select the Sub Capabilities you want to be displayed.
  - Click **Select All** to display all removed Sub Capabilities.
3. Click **Apply**.

## Removing Capabilities

To remove a Capability from the chart

1. Select a Capability.
2. On the diagram toolbar, click the **Remove From Chart** button.

To delete a Capability from the model

1. Select a Capability.
2. On the diagram toolbar, click the **Delete** button.

## Removing Sub Capabilities

To remove a Sub Capability from the chart

1. Select a Sub Capability.
2. On the diagram toolbar, click the **Remove From Chart** button.

To delete a Sub Capability from the model

1. Select a Sub Capability.
2. On the diagram toolbar, click the **Delete** button.

## Editing Capability Provision

To edit Capability Provision

1. Right-click the Capability.
2. Select **Edit Capability Provision**.
3. Choose the Capability Provision which you want to edit. The **Capability Provision Creation Wizard** opens.
4. Edit the dates.
5. Click **Finish**.

## Removing Capability Provision

To remove Capability Provision

1. Right-click the Capability.
2. Select **Remove Capability Provision**.
3. Click the Capability Provision which you want to remove from the chart.