

# Installation

Before installing Connex DDS for MagicDraw, first install RTI Connex DDS by following the instructions in its [Getting Started guide](#).

To install Connex DDS for MagicDraw

---

1. Install [MagicDraw](#).
2. Install [SysML plugin](#).
3. Start MagicDraw.
4. On the main menu, click **Help > Resource/Plugin Manager**.
5. Click **Import** and select the *Connex DDS for MagicDraw plugin* archive (*connex-dds-magicdraw-plugin.zip*).
6. After the successful installation, restart the MagicDraw.