


Setting up Automatic Population of Measurement Sets


You can set up the automatic measurementSet population each time creating the Instance of the associated type.

To set up the automatic Measurement Set population

1. Create a Measurement Set.
2. Add measurements for the created Measurement Set.
3. Apply «DoDAF Properties» stereotype to the created Measurement Set.
4. Open the Measurement Set Specification window and make sure the Expert properties mode is selected.
5. In the **Tags** property group, select the appliesFor and click the **Create Value** button.
6. Select the Exchange Element stereotype as the **appliesFor** tag value.



7. Save and reload the project.

 You can see and edit your custom measurements.

