


# General

DataHub allows you to select default options for mapping type and policy, filter, and synchronization through the **General** option group.

To modify the DataHub **General** option group

1. Open the **Cameo DataHub Options** dialog.



2. Under the **General** option, choose when validating and fixing DataHub database happen, select or clear the option of data synchronization when saving a project, setting the Group Type mapping as default, or filtering a MagicDraw Data Source from DataHub Explorer. If you want to select an option to display the mapping dialog, select one of the options in the **Mapping policy** drop-down list.
3. Click **OK**.

The following table explains the detail of Cameo DataHub options in the **General** option group

Option	Function
<b>Validate and fix DataHub database when</b>	Shows options of when validating and fixing DataHub database happen in the drop-down list as follows <ul style="list-style-type: none"><li>• Cleaning up DataHub database</li><li>• Starting DataHub and cleaning up DataHub database</li><li>• Never</li></ul>
<b>Synchronize data when saving project</b>	Enables automatic synchronization with MagicDraw® when you save a project.
<b>Set the Group Type Mapping as the default mapping</b>	Sets the default mapping to group type mapping when copying data.
<b>Filter a MagicDraw data source from DataHub explorer</b>	Hides the display of MagicDraw® Data Sources in DataHub Explorer and shows the Data Sources when cleared.

<b>Mapping policy</b>	<p>Shows options of displaying the mapping dialog that you can select in the drop-down list as follows</p> <ul style="list-style-type: none"><li>• Always show the mapping dialog</li><li>• Show mapping for elements without default mapping</li><li>• Show mapping for elements that cannot be automatically mapped</li><li>• Show mapping for elements with an unknown data type</li><li>• Treat no-default mapping element as exclude.</li></ul>
-----------------------	--