Working with Activity diagram

On this page

- Behavior Creation Mode
- Creating Actions by pasting the copied list
- Smart layout
 - Dynamic centerlines
 - Diagram orientation
- Deleting from Activity diagrams
- Displaying inner elements

Behavior Creation Mode

You can use the **Behavior Creation Mode** to automatically create an Activity after creating a Call Behavior Action in the Activity Diagram. The newly created Activity will be set as the behavior of the Call Behavior Action.

To turn on the Behavior Creation Mode in an Activity diagram




- A Behavior is created together with the Call Behavior Action. It inherits the type of the Call Behavior Action owner.
- If a Call Behavior Action and its Behavior are not titled, type a name on the Call Behavior Action shape on the diagram, and the typed name will be set as the Behavior's name automatically.

Creating Actions by pasting the copied list

You can copy the item list from the text editor (Word, Notepad, etc.), web page, PDF file, and paste it in the Activity diagram to create actions.

To create Actions by pasting items from the list

- 1. Copy the list.
- 2. Go to the diagram and press Ctrl+V.
- 3. Select an Action.
- 4. In the question dialog click Yes if you need to connect the Actions with Control Flow relationship.




Smart layout

Dynamic centerlines

The centerlines are displayed only when the center of the shape that was moved or newly drawn is located near the center of a preexisting shape in the diagram. These lines help you to easily align shapes when drawing a diagram.

When the center of the shape that was moved coincides with a center of any shape that is placed to its right or left, a horizontal centerline appears. When the center of the shape is close to any center of a shape that is located above or below it, a vertical centerline appears.




To switch off the dynamic centerlines

- Click the Show Centerlines button $\stackrel{re}{\hookrightarrow}$ in the diagram toolbar, or press C.
- From the **Options** main menu, select **Environment**. In the **Environment Options** dialog, click the **Diagram** category, and clear the **Show** Centerlines in Flow Diagrams check box in the **Display** properties group.

Diagram orientation

The diagram orientation is used to assign the correct rectilinear path breaks and draw paths between the Activity diagram shapes. The paths can be drawn from side to side, or from the lower to the upper shape borders.



Related pages

- Creating diagrams
- Dragging in Activity diagrams
- Creating elements from other resources